

NASA / ⁻⁹⁶⁻
CR-203908

FINAL
TN-19-CR

FINAL REPORT

NAS5-30549

SOFTWARE
for the
HYDRA INSTRUMENT ON THE POLAR SPACECRAFT

MODETHREE
September 29, 1996

UNIVERSITY OF CALIFORNIA, SAN DIEGO

c:\1\hydra\rpt\fin\fidtitle.FID
c:\1\hydra\rpt\fin\CONTENTS.FIN
c:\1\hydra\fid_0\TSKINT_0.FID
c:\1\hydra\fid_0\RSORC_0.FID
c:\1\hydra\fid_0\SOWPGM_0.FID
C:\1\HYDRA\FID\RESYNCH.INT
c:\1\hydra\fid_2\PEAKDWEL.FID
c:\1\hydra\fid_2\HVDUMPX.FID
c:\1\hydra\fid_2\SCSQ_2E.SEQ
c:\1\hydra\fid_0\DSHV100.TAB c:\1\hydra\fid_0\DFLSV001.TAB
c:\1\hydra\fid_2\B2PPA_2.FID c:\1\hydra\fid_0\APXB2PPA.FID
C:\1\HYDRA\PAS\GRIDABAB.COD
C:\1\HYDRA\FID_3\HVMON_3.FID
C:\1\HYDRA\FID_3\PHA_3.FID
c:\1\hydra\fid_0\TLM_0.FID
c:\1\hydra\fid_0\PSRL1610.FID
c:\1\hydra\fid_3\S175_3.FID
c:\1\hydra\fid_0\TIMMTX_0.FID
c:\1\hydra\fid_0\TIMLIN.FID
c:\1\hydra\rpt\fin\tlmtitle.FID
c:\1\hydra\tlmf_0\tlmall_0.fid
c:\1\hydra\tlmf_0\tlmalc_0.fid
c:\1\hydra\tlmf_0\mfost_0.fid
c:\1\hydra\tlmf_0\tlmd_0.fid
c:\1\hydra\tlmf_0\tlmpp_0.fid
c:\1\hydra\tlmf_0\tlmp_0.fid
c:\1\hydra\tlmf_2\tlmsn_2.fid
c:\1\hydra\tlmf_3\tlmlb_3.fid

TSKINT_0.0. Task and Interrupt List for ModeZero
September 29, 1996

TSKINT_0.0.1. Nomenclature for Hydra Timing Intervals

| | |
|-----|---|
| BCI | Basis Cycle Interrupt (programmable) |
| BFR | Magnetometer data refresh cycle |
| BSP | Magnetometer sample period |
| DDC | DDEIS accumulation interval |
| DDN | DDEIS energy step interval |
| DSC | DDEIS energy scan period (programmable) |
| ET2 | Experiment timing signal #2, generated internally |
| MJF | Major Frame Period |
| MNF | Minor Frame Period |
| PPC | PPA accumulation interval, summed in scratch RAM over some number of PPR cycles, and read out to telemetry. |
| PPL | The live accumulation portion of the PPR |
| PPR | PPA RAM refresh interval (readout and reset the 8 bit RAM on the PPA board.) |
| PSC | PPA energy scan period (programmable) |
| SEC | One NBS standard second |
| SPT | Tick of spin phase reference clock (4096 per sun reference pulse) |
| SUN | Sun reference pulse (=spin period) |
| TMT | Tick of the 55652 hz telemetry clock |

TSKINT_0.1.0. Tasks

TSKINT_0.1.1. DDSCAN_0

Initiated after each BCI, and must complete before the next BCI. Moves 12 16-bit readings from DDHOTBUF into DD16_BUF. Determines the Control Vector for the next accumulation of the DDEIS. 1 MJF = 16 DSC. 1 DSC = 16 DDC. 1 DDC = 2000 TMT.

TSKINT_0.1.2. PPSCAN_0

Initiated after each BCI, and must complete before the next BCI. Counts PPR's and determines the Control Vector for the next PPC. Checks overflow bit, and, for no overflow, performs replace-adds of the 256 8-bit accumulations from PPHTOTBUF into 256 16-bit RAM accumulators, PP16_BUF. Copies old values of theta, phi, and overflow bit from PPTHETAPHI_OLD to the appropriate two byte location in TPV_BUF. 1 MJF = 4 PPC. 1 PPC = 128 PPR. 1 PPR = 1000 TMT.

TSKINT_0.1.3. B2PPA_0

Saves previous values of theta and phi to PPTHETAPHI_OLD. Takes readings from the magnetometer reading

stack, extrapolates to the time of the upcoming PPR, and computes new PPA control coordinates theta and phi. The next BCI copies these values to the PPA board for the next PPR, reads the overflow bit from the PPA board for the last PPR, and writes the overflow bit to the high order bit of PPTHETAPHI_OLD. Enabled by the PPSCAN_0 task and run right after it. It must be completed in time for the ET2 interrupt that ends the PPR.

TSKINT_0.1.4. TLM_0 (TLMOTASK)

Takes data from the holding-processing buffers, packs them, and writes the packed data into the telemetry buffer. Task TLM_0 must not read data until after PPSCAN_0 and DDSCAN_0 have completed filling half of their holding-processing buffers PP16_BUF and DD16_BUF, and it must not write data into the telemetry buffer until the telemetry task has cleared the last half. To assure these conditions, TLM_0 is started 4 times per MJF by PPSCAN_0 8 BCI's after at the end of each PPC. TLM_0 must complete by the end of the next PPC. It fills TMBUF in the order of 256 bytes (PPTPV), 150 bytes (PPTMBINS), 960 bytes (DDTM), and 4 or 3 remaining bytes for even and odd quarters, respectively.

TSKINT_0.2.0. Interrupts

TSKINT_0.2.1. Hardware Interrupts

TSKINT_0.2.1.1. BCI

Receives theta and phi from the B2PPA_0 task and delivers them to the PPA. Starts the PPA. Receives Control Vectors from the PPSCAN_0 and DDSCAN_0 tasks and delivers them to PPA and DDEIS. Unloads DDEIS accumulators. Starts PPSCAN_0 and DDSCAN_0 tasks. Initiated by BCI counter, which is clocked by telemetry clock. Period 1000 TMT. Reset by MJF.

TSKINT_0.2.1.2. ET1

Not used by Hydra in ModeZero.

TSKINT_0.2.1.3. ET2

Turns off the PPA on the fourth, second, or first ET2 within a PPR. Subdivides the PPR interval and halves it in response to overflows. On the fourth ET2 within a PPR, unloads the 256 8-bit accumulators on the PPA board into a buffer, PPHOTBUF, and sends the next HV value to the PPA. Initiated by ET2 counter, which is clocked by telemetry clock and reset by MJF. Clocked by telemetry clock. Period 200 TMT.

TSKINT_0.2.1.4. DUN

Delayed sun pulse. Resets ET1 via hardware connection.
Calls for a time reading.

TSKINT_0.2.1.5. MJF

Initiated externally each major frame. Resets several pointers. Calls for a time reading.

TSKINT_0.2.1.6. MNF

Reads 23 or 22 bytes of data from the science buffer and 0 or 1 byte from the housekeeping buffer into the hardware FIFO in the proper sequence to present the proper housekeeping data for each slot in the telemetry frame. Occurs at the beginning of each minor frame and must be completed before the first telemetry word gate. Initiated externally each minor frame.

TSKINT_0.2.1.7. BXYZ

The magnetometer ISR collects the magnetometer readings and filters them. Each reading consists of 4 components, Timing/status, Bx, By, and Bz. The same filter algorithm is applied individually to Bx, By, and Bz. Initiated externally 16 times per MNF.

In ModeZero, the form of the filter is

$$O(i) = (1-a)*O(i-1) + a*I_i$$

where O represents the Output of the filter, I represents the Input to the filter, a is a fraction representing the weight given the current input (e.g.: 1/8), 1-a is a complementary fraction representing the weight given the past values (e.g.: 7/8), (i) represents the current value, and (i-1) represents the most recent value. The optimum value of a is TBD. The most compact code is produced if a = 1/2, and so it will be set to this value unless it proves unsatisfactory in operation with test data.

In higher modes, the filter is a Kalman filter as described in BLR2PPA.

TSKINT_0.2.1.8. TC

Initiated externally once per second. Reads a 4 byte Universal Time Code Word from the spacecraft timer, and places it in a UTC register.

TSKINT_0.2.2. Special Software Functions

TSKINT_0.2.2.1. Time Reading

At particular times, a time mark is obtained by reading the 4 byte UTC time mark and the 2 byte millisecond counter. Time readings are made by the MJF ISR, and the DUN ISR.

TSKINT_0.2.2.2. Scan Resynchronization

At the end of a certain number of major frames, the ddscan and ppscan routines re-execute their initialization sections to make them start over at the beginning of the scanning sequence. The proper number of major frames is called the Sequence Resynchronization Interval, and is a RAM variable. The Sequence Resynchronization Interval is chosen so that the sequence has executed a complete cycle, and it should be back at the start without being told. Thus this is only what should happen, but the resynchronization is to get back on schedule in case there are any glitches. The calculation of the Sequence Resynchronization Interval is discussed in Section SCNSEQ_0.1., SCNSEQ_0.4.3., and SCSQ_0.5. Values are given in those sections that are appropriate for the scan sequences described therein.

This is implemented as follows:

At the beginning of its power-up initialization section, the ddscan routine saves synch_mjf = the low byte of the MJF counter + synch_interval. Near the end of each execution of ddscan, it checks the BCI counter and the major frame counter maintained by the BCI and MJF ISRs, respectively. (See SOWPGM_0.0.) If it is the last BCI of a major frame, and the major frame is equal to the saved resynch frame, 'resynch' flags are set for itself and the ppscan routine, and the ddscan routine branches to its initialization code. In the initialization code, a couple of things are done differently than they would be for a true initialization because of the fact that an accumulation should be about to end and we will want to get the data next BCI. When the ppscan routine runs, it checks its resynch flag at the end, and if it is set, re-executes its initialization code, also with some slight variations from what it would do for a true initialization.

TSKINT_0.3.0. Special Hardware Functions

TSKINT_0.3.1. Telemetry Wordgate

Reads out the hardware FIFO.

TSKINT_0.3.2. DUN

Resets ET1.

TSKINT_0.3.3. MJF

Resets BCI counter and ET2 counter.

TSKINT_0.3.4. SUN

The Sun Pulse from the spacecraft resets the Delayed Sun Pulse (DSP) counter, which counts the spin clock.

RSORC_0.0. Resource Usage by Hydra Software
September 29, 1996

RSORC_0.0.1. Memory Allocation

| | | |
|----------|--------|--------------|
| 8K x 8 | PROM | Firmware |
| 32K x 8 | RAM | Rad-Hard |
| 128K x 8 | EEPROM | Software |
| 1M x 8 | RAM | Burst Memory |

RSORC_0.1.0. RAM, ModeZero

In order to provide another degree of robustness, the 32K X 8 rad-hard RAM will be split into two banks, switchable upon command. ModeZero will use only one bank, allowing a redundant backup bank to be called in case of a failure in the primary RAM. Forth will reside in the backup, or secondary, half of rad-hard RAM. Because Forth builds from zero, this must be the lower half. Thus the primary half will be the upper half.

RSORC_0.1.1. Raw-Data Buffers

RSORC_0.1.1.1. Hot-Data Buffers


P_INBUF (equivalent to IN_BUF): Pointer to the start of the hot-data buffers, DDHOTBUF and PPHOTBUF. PPHOTBUF starts 28 bytes after DDHOTBUF.

DDHOTBUF: DDEIS accumulator dump. 14 channels at 16 bits per reading. Loaded by BCI when told to by DDSCAN control vector. Unloaded by the next DDSCAN into DD16_BUF. This buffer and data transfer could be eliminated if BCI loaded DD16_BUF directly. Size = 28 bytes.

PPHOTBUF: 256 X 8 bit buffer to catch the image of the 8 bit accumulators on the PPA board. Loaded by interrupt ET2. Unloaded by the next PPSCAN into PP16_BUF. Size = 256 bytes.

THETAPHI: Values of theta and phi for the next PPR.
Values created by B2PPA. 2 bytes.

THETAPHI_OLD: Values of theta and phi for the last PPR, copied by B2PPA from THETAPHI. The BCI ISR writes the value of the overflow bit in the 16th bit. PPSCAN writes the 2 byte result into TPV_BUF. The following is an attempt to diagram the flow of theta, phi, the overflow bit, and some of the data.



RSORC_0.1.1.2. Holding-Processing Buffers

DD16_BUF: DDEIS accumulator ring buffer. 12 channels for 128 DDC's at 16 bits per reading = 3072 bytes. Loaded from 12 words of DDHOTBUF by DDSCAN. Unloaded by DD2TM. Treated by DDSCAN as a ring buffer of length 128 DDC's; treated by DD2TM as a ring buffer of length 2*64, or double buffer. Size = 3072 bytes.

PP16_BUF: PPA 16 bit accumulator. PPHTBUF is replaced added into PP16_BUF by PPSCAN. 16 bits for each of 256 bins, double buffer. Size = 1024 bytes.

TPV_BUF: PPA theta, phi, and overflow data: 2 bytes per sector, 128 sectors per accumulation, double buffer. Size = 512 bytes.

DDWILLISWAS: Not implemented in ModeZero.

PPWILLISWAS: Not implemented in ModeZero.

RSORC_0.1.2. Telemetry Buffers

RSORC_0.1.2.1. TMBUF

A buffer loaded by task DATA2TMZ and unloaded by the MNF interrupt service routine (ISR). This ISR removes 22 bytes on each MNF interrupt except the first. Since there are 250 MNF's per MJF, this is $22 \times 249 = 5478$ bytes per MJF, of the 5739 total science telemetry allocated to Hydra. The length of TMBUF is half of the 5478, or 2739 bytes. TMBUF is loaded in two parts, like a double buffer. Each part contains, in order,

| | | |
|----------------------|--------------------|-------|
| PPTPVTM | 256 | bytes |
| PPTMBINS | 150 | bytes |
| DDTMBUF | 960 | bytes |
| Science Housekeeping | 4 or 3 | bytes |
| | 1370 or 1369 bytes | |

1370 + 1369 = 2739 bytes

PPTPVTM: Half, or 256 bytes, of TPV_BUF are moved at a time from TPV_BUF to PPTPVTM without any modification.

PPTMBINS: 120 bins are compressed (PSRL 16 to 10) by CS8to5 and packed into 1200 bits or 150 bytes.

DDTMBUF: 12 channels at 10 bits per reading for 64 DDC's at a time. Size = 960 bytes.

RSORC_0.1.2.2. LOOSEBYTES

The "loosebytes" are the telemetry allocation consisting of word 17 in minor frames 1-139. We have assigned these bytes for science housekeeping. They will be held in a double buffer of length 278 bytes. When the major frame counter, MJF_CNT, is even, the lower half is read out and the upper half is filled. When MJF_CNT is odd, the upper half is read out and the lower half is filled. The first byte, byte zero, of each half buffer will be written by UNH. The remaining 138 bytes will be written by UCSD. The buffer will be read out by the minor frame interrupt service routine.

RSORC_0.1.3. Total Buffer Space

| | DDEIS | PPA | TVO | SHKPG |
|-------------------|-------|------|------|-------|
| Hot Data | 28 | 256 | 4 | 288 |
| Holding Data | 3072 | 1024 | 512 | 4608 |
| Telemetry Buffers | 1920 | 300 | 512 | 285 |
| | ---- | ---- | ---- | ---- |
| Total | 5020 | 1580 | 1028 | 285 |
| | | | | 7913 |

RSORC_0.2.0. PROM Usage

9/6/91

| | |
|---------------|-------------------|
| DDSCAN_0 | approx 605 bytes |
| PPSCAN_0 | approx 719 bytes |
| B2PPA_0 | approx 793 bytes |
| DATA2TM_0 | approx 735 bytes |
| Descr. Tables | approx 38 bytes |
| Total | approx 2890 bytes |

9/17/91

| | |
|---------------|-------------------|
| DDSCAN_0 | approx 274 bytes |
| PPSCAN_0 | approx 435 bytes |
| chk_sc_es | approx 153 bytes |
| next_descr | approx 127 bytes |
| B2PPA_0 | approx 797 bytes |
| DATA2TM_0 | approx 756 bytes |
| Descr. Tables | approx 39 bytes |
| Total | approx 2581 bytes |

9/19/91

| | |
|-------|------------|
| Total | 2479 bytes |
|-------|------------|

9/25/91

| | |
|---------------|------------------|
| Descr. Tables | approx 39 bytes |
| DDSCAN_0 | approx 200 bytes |
| PPSCAN_0 | approx 353 bytes |
| chk_sc_es | approx 140 bytes |
| next_descr | approx 127 bytes |
| descr_init | approx 67 bytes |

| | | |
|-------|-----------|-------------------|
| | B2PPA_0 | approx 705 bytes |
| | DATA2TM_0 | approx 715 bytes |
| Total | | approx 2346 bytes |

SOWPGM 0.0. DIAGRAM OF A ROUTINE
FOR OPERATION OF THE HYDRA SCANNING ANALYZERS

MODEZERO
September 29, 1996

A scanning sequence is begun by a command which provides the starting descriptor number. The command handler saves the descriptor number, and sets an init_flag for the scanning program. The scanning routines run once to initialize, and then don't run again until the next MJF. Subsequently they run every BCI until another command restarts the sequence.

The BCI ISR calls the scanning routines after each Basis Control Interrupt (BCI)

Test the init_flag to see if an external command arrived to start a new descriptor series.

No

Yes |

DD: Calculate and save synch_mjf
= the low byte of the MJF counter + synch_interval
Default value of synch_interval is 63, changeable by upload.

* RESYNCH REENTRY *

Copy ROM descriptors to RAM
Get descriptor # left by command processor
Get # interrupts/accumulation from descriptor and increment by 1 because this interval (i.e., next interrupt) doesn't count.

DD: If last BCI before MJF, and if low byte of MJF counter matches synch_mjf, then set PP and DD resynch flags and recomputes synch_mjf.

PP: Enable magnetometer task

PP: Replace-add 256 8-bit data words from PPHOTBUF
into 256 16-bit bins in PP16BUF iff no overflow
PP: Move 15 bits of theta and phi + ovflow bit to TPV_BUF

| Did an accumulation end at the last interrupt?

| No

| Yes

DD: Complement down-count to count and
move data from hot-data buffer
to holding-processing buffer
PP: Swap double-buffer pointers
PP: Initialize tlm-delay counter to 8

| Will scan finish at next interrupt?

| No

| Yes

| Will an energy step finish at next interrupt?

| No

| Yes

PP: Copy HV to science housekeeping buffer
Compute voltage index number for next energy
level, put in control vector, and turn on
new HV flag in control vector.

| Will this accumulation end at next interrupt?

| No

| Yes

Set acc_clear bit in control vector
(affects DDEIS only)

| PP: Copy HV to science housekeeping buffer

| Will offset cycle finish at next interrupt?

| No

| Yes

Increment current descriptor's
running offset for its next scan
Get next scan descriptor number

| Get next cycle descriptor number |

| Get scans/offset cycle from descriptor
| Re-initialize current descriptor's running offset
| to zero |

| Get # interrupts/energy step from descriptor.

| Compute # interrupts/energy scan

| = (interrupts/Estep)*(Esteps/scan).

| Initialize parameters for pyramid scan profile.

| Load control vector:

| Set acc_clear bit (used by DD only)

| Set new_hv bit

| Set polarity bit (used by DD only)

| Copy scan base energy from descriptor,
| add offset base from descriptor,
| and add running offset to obtain next HV level.

| Check individual (DD or PP) resynch flag. Time to resynch? |

| No |

| Yes |

* GO TO RESYNCH REENTRY *

| DD: Format HV index for DAC scale |

| Copy HV index to control vector |

| PP: Decrement and test tlm-delay counter.

| Enable telemetry task if zero. |

| Return |

DESCRIPTOR LIBRARY

CONTROL VECTOR

Flags (TBD bytes)

DDEIS

| | |
|---|----|
| DDEIS Sensor Polarity (1 bit action flag + 1 bit value) Change DDEIS HV on next BCI (1 bit action flag + 6 bits value + 1 bit polarity -- 0 negative, 1 positive --) Clear DDEIS accumulators on next BCI (1 bit action flag) | @! |
|---|----|

PPA

| | |
|--|----|
| Change PPA HV on next ET2 (1 bit action flag + 7 bit value) | @! |
|--|----|

HV DAC Values

| | |
|---|----|
| DDEIS HV DAC Value (64 steps, or 6 bits + range + polarity = 8 bits) PPA HV DAC Value (128 steps, or 7 bits) | @! |
|---|----|

These HV DAC control bytes are obtained from the HV RAM lookup tables.
See SCNSEQ_0.5.

SCAN VECTORS

DDEIS SCAN VECTOR, MODEZERO

| Descriptor Number | DD0 | DD1 | # bytes |
|---|-----|-----|---------|
| Scan Base Level | 127 | 128 | 1 |
| 0 <= Base <= 255 (internal scale) | | | |
| Scan Increment | +4 | -4 | 1 |
| Number of HV Steps | 21 | 21 | 1 |
| Per Scan (DDN's/DSC) | | | |
| Offset Base (+-Levels) | 0 | 0 | 1 |
| Offset Increment (+-) | +1 | -1 | 1 |
| Scans Per Offset Cycle | 4 | 4 | 1 |
| # Interrupts per Energy Step (BCI's/DDN) | 2 | 2 | 2 |
| # Interrupts per Accumulation (BCI's/DDC) | 2 | 2 | 2 |
| Number of Next Scan Descriptor | DD1 | DD0 | 1 |
| Number of Next Cycle Descriptor | DD1 | DD0 | 1 |
| Sensor Polarity | + | - | 1 |

PPA SCAN VECTOR

| | | |
|--|-------------|---------|
| Descriptor Number | PP0 | # bytes |
| Scan Base Level 0 <= Base <= 127 | 85 | 1 |
| Scan Increment | 2 | 1 |
| Number of HV Steps Per Scan | 18 | 1 |
| Offset Base (+-Levels) | 0 | 1 |
| Offset Increment (+-) | 1 | 1 |
| Scans Per Offset Cycle | 2 | 1 |
| # Interrupts per Energy Step (BCI's/PPN) | 128 | 2 |
| # Interrupts per Accumulation (BCI's/PPC) | 128 | 2 |
| Address of Next Scan Descriptor | PP0 | 1 |
| Address of Next Cycle Descriptor | PP0 | 1 |
| Sensor Polarity | (null byte) | 1 |

| HARDWARE TIMING CONTROLS | Hex | Dec |
|--|---------|--------|
| Value in Basis Control Int. Counter (BCI) | 3E8 | 1000 |
| Value in 1st Expt. Timing Counter (ET1) | FF | -1 |
| Value in 2nd Expt. Timing Counter (ET2) | C8 | 200 |
| Value in Acc. Gate Counter (ACC) | BB80 | 48,000 |
| Value in Sun Pulse Delay Counter (DSP) | 01 | 1 |
| Value in Time Code Counter | FF | -1 |
| BCI Select MUX Setting | TM | |
| MIT Select MUX Setting | non-MIT | |

| | |
|------------------|---------|
| TELEMETRY VECTOR | |
| Data Word Length | 10 bits |

@! Loaded by program in real time.

RESYNCH.0. Calculating the Resynchronization Interval

The criterion for determining the resynchronization interval is that it must contain an integer number of PPA cycles, DDEIS cycles, and telemetry cycles. Define:

```
F = # MJF's/resynchronization interval
Sp = # PPA cycles/resynchronization interval
S+ = # DDEIS ion cycles/resynchronization interval
S- = # DDEIS electron cycles/resynchronization interval
Sd = # DDEIS ion + electron cycles/resynchronization interval
Np = # HV steps/PPA cycle
N+ = # HV steps/DDEIS ion cycle
N- = # HV steps/DDEIS electron cycle
Nd = (N+) + (N-) = # DDEIS steps/DDEIS ion + electron cycle
```

We have allocated our ModeZero Code telemetry space into 256 DDEIS readings and 4 PPA readings per MJF, and we have partitioned the DDEIS readings between ions and electrons:

$$N^- + N^+ = Nd$$

$$S^- = S^+$$

The essential constraint on the sequence resynchronization interval, F, is that it must contain an integral number of both PPA scans and DDEIS scans. When this constraint is met, the resynchronization occurs seamlessly. In addition to tidiness, this prevents the resynchronization from occurring in the middle of a scan, and calling for some large step from either of the HV power supplies. This constraint (actually two constraints) gives two integer equations:

$$\begin{array}{ll} 256 * F = Sd * Nd & \text{or} \\ 4 * F = Sp * Np & \text{or} \end{array} \quad \begin{array}{ll} 2^{**8} * F = Sd * Nd \\ 2^{**2} * F = Sp * Np \end{array}$$

Eliminating F gives another integer equation which must be satisfied for integers Sp, Sd, Np, and Nd:

$$2^{**6} * Sp * Np = Sd * Nd$$

Given Nd and Np, this integer equation can be solved by inspection, which is easy if one first factors all integers into their prime factors.

For example, for Scan2E, the descriptors will be predicated on a value of 256 for Nd ($3*43 + 3*41 + 4$). The value for Np will be 36, or all the levels spanning the particle energy interval from 500 eV to 5 keV. Thus, we have

$$\begin{array}{l} Nd = 256 = 2^8 \\ Np = 36 = 2^2 * 3^2 \end{array}$$

and we must satisfy the following integer equation:

$$2^6 * Sp * 2^2 * 3^2 = Sd * 2^8$$

By inspection, this equation is satisfied if $Sd = 3^2$ and $Sp = 1$. This gives us the length of the resynchronization cycle, $F = 3^2 = 9$.

For the general case, although there may be overriding considerations, we prefer a short resynchronization interval, and the ModeZero code burned into ROM allocates only one byte for the value of F . The above demonstrates that Nd must be factored by several powers of two in order for this to be possible, and that it also helps if Nd and Np contain some prime factors in common.

PEAKDWEL.0. Strategies for Energy Dwells
September 29, 1996

PEAKDWEL.1. Dwells

Descriptors for which the Scan Base Level = -1 or 255 (Note that -1==255) are called dwell descriptors. At execution time, the code will use the offset of the peak level in place of the Scan Base Level. These are called dwell descriptors because one application is to let the voltage dwell for an extended time at the peak level from the previous scan. Because of the generality of the descriptor algorithm, it is also possible to base new scans on the peak level. In this case it is really a scan with a base level computed at run time, and dwell is probably a misleading term.

PEAKDWEL.2. Peak Seeking Scans

For each offset cycle, the scan program determines the level at which the peak weighted counting rate occurred. This is done by finding the maximum counting rate for each DDC, and comparing this value, multiplied by an optional weight, with a running maximum. The program retains the scan offset and HV control byte of the maximum. The weight is obtained from a table of length 64 indexed by the 6 LSB's of the control hexbyte.

The entries in the weight table are proportional to the energy of the particle to which the analyzers are tuned, but they are shifted somewhat to accommodate the integer arithmetic restrictions of the CPU:

| Decimal Value of 6 LSB's | DDEIS Tuned Energy | Weight | Decimal Value of 6 LSB's | DDEIS Tuned Energy | Weight |
|--------------------------|--------------------|--------|--------------------------|--------------------|--------|
| 0 | 7.07 eV | 6 | 32 | 534 | 484 |
| 1 | 8.2 | 7 | 33 | 616 | 558 |
| 2 | 9.3 | 8 | 34 | 708 | 641 |
| 3 | 10.8 | 10 | 35 | 808 | 731 |
| 4 | 12.3 | 11 | 36 | 928 | 840 |
| 5 | 14.2 | 13 | 37 | 1065 | 964 |
| 6 | 16.3 | 15 | 38 | 1223 | 1107 |
| 7 | 18.7 | 17 | 39 | 1404 | 1271 |
| 8 | 21.1 | 19 | 40 | 1571 | 1422 |
| 9 | 24.3 | 22 | 41 | 1811 | 1640 |
| 10 | 27.9 | 25 | 42 | 2081 | 1884 |
| 11 | 32.0 | 29 | 43 | 2374 | 2149 |
| 12 | 36.7 | 33 | 44 | 2729 | 2471 |
| 13 | 42.1 | 38 | 45 | 3131 | 2835 |
| 14 | 48.3 | 44 | 46 | 3596 | 3255 |

| | | | | | |
|----|------|-----|----|-------|-------|
| 15 | 55.3 | 50 | 47 | 4125 | 3734 |
| 16 | 61.9 | 56 | 48 | 4616 | 4179 |
| 17 | 71.5 | 65 | 49 | 5323 | 4818 |
| 18 | 82.2 | 74 | 50 | 6117 | 5537 |
| 19 | 93.6 | 85 | 51 | 6995 | 6332 |
| 20 | 107 | 97 | 52 | 8019 | 7259 |
| 21 | 124 | 112 | 53 | 9200 | 8328 |
| 22 | 142 | 128 | 54 | 10563 | 9562 |
| 23 | 163 | 147 | 55 | 12115 | 10967 |
| 24 | 182 | 165 | 56 | 13592 | 12304 |
| 25 | 210 | 190 | 57 | 15667 | 14182 |
| 26 | 241 | 219 | 58 | 17997 | 16292 |
| 27 | 276 | 249 | 59 | 20525 | 18580 |
| 28 | 317 | 287 | 60 | 23575 | 21341 |
| 29 | 363 | 329 | 61 | 27037 | 24475 |
| 30 | 417 | 378 | 62 | 31015 | 28076 |
| 31 | 479 | 433 | 63 | 35555 | 32186 |

Peak seeking is implemented for DDEIS scans only. PPA dwells are based upon DDEIS electron peaks. This means we need to keep separate peaks for positive and negative scans, so that the electron peak is always ready for the PPA when it needs it in its good time. Because of the arrangement of HV RAM Lookup Table DSHV900.TAB, the offset to an electron peak must lie between 127 and 63, with 63 being the highest energy. Actually, because of the limitation explained in PEAKDWEL.3.1., the offset to an electron peak should lie between 127 and 81, inclusive, corresponding to electrons in the energy range from 7.07 to 3596 eV. According to DFLSV001.2., the PPA is tuned to this energy range from steps 22 (6.91 eV) to 114 (3469 eV). Thus an algorithm for computing the PPA level corresponding to a DDEIS offset is

$$\text{PPoffset} = 276 - 2 * \text{DDoffset}$$

However, a PPA voltage step from level 0 to any level above 96 violates that power supply's single-step limitation. Therefore, when PPA dwell descriptors are in the loop, the DDEIS electron levels should be limited to 127 to 90.

At the end of each offset cycle, write both the HV table index and the control hexbyte corresponding to the peak to a memory location to be picked up by telemetry. As long as we read out this value before the dwell is over, we get the scan base value for the dwell. Otherwise, we have no way of knowing the level at which the dwell took place. See TLMF.TLMLB_2. for the position of these values in the Science Housekeeping Loose Bytes.

PEAKDWEL.3. Restrictions in the Use of Energy Dwells

PEAKDWEL.3.1. Limits on the Ranges of Peak-Seeking Scans

Before the beginning of a dwell, the deflection power supplies are at some low level from the end of the previous scan. The next level is computed, using the peak level as Scan Base level. We are concerned lest this computed level create too large a jump for the deflection power supplies to handle safely in one step. We can restrict this jump if the peak-seeking scans include only levels that we can jump to safely. As a step of 1100 v is used by the DDEIS in SCSQ_2E, we will allow this big a jump, but no higher, for a DDEIS dwell. Thus the peak-seeking scan for a DDEIS dwell is limited to levels 0-46. These levels correspond to table offsets of 127-81 in the designated Table DSHV900.TAB. Similarly, the peak-seeking scan for a PPA dwell is limited to DDEIS offsets from 127 to 90 in Table DSHV900.TAB.

PEAKDWEL.3.2. Number of HV Steps per Accumulation Interval

During peak-seeking scans, use only one HV step per DDC so as not to confuse the position of the peak.

PEAKDWEL.3.3. HV RAM Lookup Table DSHV900.TAB

Table DSHV900.TAB is tailored for dwell descriptors. The high ranges are the only ones expected to be used, and they are arranged to be straightforward so that dwell scans take place in a reliable sequence.

| Offset Range | Label | Sign Bit | Range Bit | Steps |
|--------------|-------|----------|-----------|-----------|
| 0 - 63 | L- | 0 | 0 | 64 steps |
| 64 - 127 | H- | 0 | 1 | 64 steps |
| 128 - 191 | H+ | 1 | 1 | 64 steps |
| 192 - 255 | L+ | 1 | 0 | 64 steps |
| Total Table | | | | 256 steps |

Use only a pre-approved HV RAM Lookup Table during peak-seeking scans and dwells. The DDEIS table contained in file DSHV900.TAB is so designated. The designated PPA table is the identity table.

Dumping ddeis HV values in mode 2

In general, ddeis HV control-byte values are saved by the ddscan routine in sequential bytes in a 256-byte array as they are used. At startup, an offset used by the telemetry task is set to the beginning of the array, and an offset used by the scan task for writing is set to byte 9. Once per quarter major frame, the telemetry task copies eight bytes to a telemetry dump buffer for actual dump the following quarter. The telemetry task then zeroes out the eight bytes from which it has copied and increments its offset to the next 8-byte segment. When the scan routine is about to save the first hv value of a cycle, it first advances to the beginning of the next segment (if it is not already on a segment boundary) and puts in 8 bytes of zeroes as a marker. It then writes the starting value at the beginning of the next segment. If any of these writes to the array would be in the next telemetry readout segment, there will be a full scan cycle delay before they take place.

Limitations:

The scan routine is generating HV values at the rate of 256 per major frame, assuming two BCIs per energy level. The telemetry task will read out and re-zero 32 bytes per major frame. As mentioned above, when writing collides with the next telemetry readout segment, writing is suspended for a cycle. If the cycle is long enough, telemetry readout can overtake writing and start dumping segments that it has previously zeroed. The shortest time in which this can occur will be when the writing collides with telemetry readout just before the readout takes place. Writing is suspended and immediately afterward (i.e., in the same BCI interval) the telemetry offset moves on to the next segment. It will then take 31 quarters for the telemetry offset to return to the segment it was in when the collision took place. During this time, the scan will have generated $31 \times 64 = 1984$ new values. In order for writing to have already moved out of this segment, it must have already written at least 8 values, so the maximum cycle length guaranteed to be written out without interruption is 1976. Experiments have shown that when the cycle is somewhat longer than this, telemetry can overtake the writing and dump the sections of the array that it has previously zeroed. When writing is able to resume, it picks up where it left off. If the cycle length is 2048, writing and readouts are in phase and no further values will be written to the array.

The following is a more detailed description of how this is implemented:

Variables and data structures used:

| | |
|-------------|---|
| dd_hv_array | 256 byte array used for storing the hv values |
| dd_hv_steps | word # of dd hv steps in a complete cycle (value set by upload) |
| dd_hv_cnt | word step # in complete cycle of hv value being set up for next |

| | | |
|------------|------|--|
| wrt_hv_cnt | word | accumulation. Values range from 0 to dd_hv_steps-1. step # in complete cycle of next hv value to be saved in dd_hv_array. The low byte of this word, added to wrt_offset, gives the byte offset at which to save. Values range from 0 to dd_hv_steps-1 for the word and 0 to min(dd_hv_steps-1,255) for the byte. |
| wrt_offset | byte | byte offset in dd_hv_array of first byte of a cycle |
| tlm_hv_cnt | byte | offset in dd_hv_array of first byte of next segment to be read out by the telemetry task |

Note: These byte values are treated as unsigned numbers ranging from 0 to 255. When two of them are added, the sum is automatically modulo 256.

Initialization:

As noted above, dd_hv_steps is initialized by upload when a new descriptor sequence is about to be commanded. At startup or descriptor command initialization, the dd scan routine sets dd_hv_cnt, tlm_hv_cnt, and wrt_hv_cnt to 0 and sets wrt_offset to 8. At re-synch time, it sets dd_hv_cnt to 0, which is what it already will be if everything is working right.

Operation:

Whenever the dd scan routine has set up a new HV value to be used on the next accumulation, including at startup or descriptor command initialization, it compares dd_hv_cnt to wrt_hv_cnt. If they are equal, it means that the HV value it has is the next one to be saved. If the next byte location to be written, indicated by wrt_offset plus the low byte of wrt_hv_cnt, is not within the next 8-byte segment to be read out by the telemetry task, it checks to see if this is the first value of a cycle, i.e., wrt_hv_cnt is 0. If it is, and if the next byte to write is not at the beginning of a segment, wrt_offset is adjusted to point to the beginning of the next segment. It then puts in 8 bytes of zeroes, and increments wrt_offset by 8. If this has not bumped it into the telemetry readout segment, or if this was not the first value in a cycle, the value is saved and wrt_hv_cnt is incremented by 1. If wrt_hv_cnt is then equal to dd_hv_steps, indicating that it has finished saving a cycle, the low byte of wrt_hv_cnt is added to wrt_offset and wrt_hv_cnt is reset to zero. The adjustment of wrt_offset is necessary to keep it moving along sequentially in the array and not jumping ahead or back. Whether it has saved a value or not, it then increments dd_hv_cnt by 1 and compares it to dd_hv_steps. If they are equal, it is at the end of a cycle, so it resets dd_hv_cnt to 0.

Once per quarter, the telemetry task copies the 8-byte segment pointed to by `tlm_hv_cnt` into a dump queue, zeroes those bytes in the array, and increments `tlm_hv_cnt` by 8.

SCSQ_2E. Candidate Deflection Voltage Sequences Compatible With
ModeTwo Code September 29, 1996

SCSQ_2E.0. Summary of Characteristics

Telemetry Allocation

DDEIS

256 DDEIS readouts (DDC's)/ MJF
12 channels per readout, 16 bits each compressed PSRL to 10 bits

PPA

4 PPA readouts (PPC's)/ MJF
120 pitch angle bins per readout
Each reading compressed PSRL 16 to 10 bits

Energy Scans

DDEIS

35.9 ms/step. Alternating scans, ions/electron.
43 levels per ion scan; 41 per electron scan. Scan increment of
3 levels at low voltages, changing to 1 level at high.
1 bipolar scan of 84 levels takes 3.019 s. Two consecutive
bipolar scans are identical, but shifted 180 degrees in
velocity space. One pair of identical bipolar scans
approximately every spin period.
Consecutive pairs offset by 1 voltage level. A cycle of 3
offsets takes 18.112 s. At the end of an offset cycle,
there is a background dwell of 8 readings to let the
look directions advance in velocity space. The angular
shift of the next offset cycle depends on the exact spin
period. If 6.00 ± 0.06 s, then 24 ± 11 degrees.
There are $3*2*(43+41)+8=512$ DDC's, or 2 MJF's, per DDEIS cycle.

PPA

Electrons only
Four levels/MJF
18 levels/scan, with step size of 2 levels
Consecutive scans offset by 1 level. 2 scans per offset cycle.
2 scans or 36 levels altogether for each cycle.
One cycle takes 9 MJF's.

COMBINED CYCLES

Period of combined cycles: 18 MJF's.
9 DDEIS cycles/combined cycle
2 PPA cycles/combined cycle


Spacecraft Timing Factors

6.00 =/- 0.06 second spin period
9.2 second major frame period (MJF)

SCSQ_2E.1. Approach to Scan Sequences

The deflection voltages are computed by an algorithm in the DDEIS and PPA scan tasks described in SOWPGM_0. What the code computes is an offset into a deflection voltage lookup table, of length 256 for the DDEIS and 128 for the PPA. The lookup tables reside in RAM and contain the HV control bytes that are sent to the deflection supplies. The lookup tables must be uploaded from the ground, and they provide the flexibility that we need to cope with uncertainty and changes in the deflection supply characteristics. It is possible to completely rewrite a scan sequence by scrambling the table; however, we anticipate that it will be used more conservatively as a fine tuning device to provide flexibility with the detailed deflection voltages, and that the scans will be designed and changed by use of the descriptor tables.

The time profile of each scan is pyramidal, which is to say that the deflection voltage ramps up and then ramps down, so that there are no end-to-end steps. The descriptor element that we call "scan increment" specifies the size of the gaps in an entire up-down scan. Most of the time, the step size will be double the descriptor scan increment, but when the 'mid' step has just finished, defined to be half of $1 + \text{the number of steps per scan}$ (integer division), then a single step must be taken, going back down if number of steps per scan is odd and going up if the number of steps per scan is even. If the next step is $\text{mid} + 1$, set the step size back to double, but make it negative to go back down. The steps may be pictured like this (E vs. t):



SCSQ_2E.2. The DDEIS Scans

The D2EComp Scan Sequence

First column 1 from top to bottom;
 then column 1 from top to bottom, again;
 then column 2 from top to bottom;
 then column 2 from top to bottom, again;
 then column 3 from top to bottom;
 then column 3 from top to bottom, again;
 then column 4;
 and then back to column 1.

| OFS | HEX | HV | OFS | HEX | HV | OFS | HEX | HV | OFS | HEX | HV |
|-----|-----|---------|-----|-----|---------|-----|-----|---------|-----|-----|--------|
| 127 | 9F | | 128 | A0 | 0.42* | 129 | A1 | * | 159 | BF | 20.62* |
| 133 | A5 | | 134 | A6 | * | 135 | A7 | * | 159 | BF | 20.62* |
| 139 | AB | | 140 | AC | 1.70* | 141 | AD | * | 159 | BF | 20.62* |
| 145 | B1 | | 146 | B2 | 3.63 | 147 | B3 | | 159 | BF | 20.62 |
| 151 | B7 | | 152 | B8 | 7.43 | 153 | B9 | | 159 | BF | 20.62 |
| 157 | BD | | 158 | BE | 17.98 | 159 | BF | 20.62 | 159 | BF | 20.62 |
| 154 | BA | 10.46 | 155 | BB | | 156 | BC | 13.68 | 159 | BF | 20.62 |
| 148 | B4 | 4.73 | 149 | B5 | | 150 | B6 | | 159 | BF | 20.62 |
| 142 | AE | 2.19 | 143 | AF | | 144 | B0 | | | | |
| 136 | A8 | 1.01 | 137 | A9 | | 138 | AA | 1.31 | | | |
| 130 | A2 | | 131 | A3 | | 132 | A4 | 0.65 | | | |
| | | | | | | | | | | | |
| 160 | C0 | 2.02* | 161 | C1 | 2.32* | 162 | C2 | 2.68* | | | |
| 166 | C6 | 4.64* | 167 | C7 | 5.35* | 168 | C8 | 5.99* | | | |
| 172 | CC | 10.45* | 173 | CD | 11.99* | 174 | CE | 13.77* | | | |
| 178 | D2 | 23.47 | 179 | D3 | 26.79 | 180 | D4 | 30.82 | | | |
| 184 | D8 | 52.14 | 185 | D9 | 60.12 | 186 | DA | 69.11 | | | |
| 190 | DE | 119.53 | 191 | DF | 137.11 | 192 | E0 | 153.13 | | | |
| 196 | E4 | 266.13 | 197 | E5 | 305.29 | 198 | E6 | 350.68 | | | |
| 202 | EA | 596.60 | 203 | EB | 680.57 | 204 | EC | 782.43 | | | |
| 208 | F0 | 1323.89 | 209 | F1 | 1526.38 | 210 | F2 | 1754.10 | | | |
| 214 | F4 | 2300.28 | 215 | F4 | 2300.28 | 216 | F4 | 2300.28 | | | |
| 220 | F6 | 3030.62 | 221 | F6 | 3030.62 | 222 | F6 | 3030.62 | | | |
| 226 | F8 | 3900.00 | 227 | F8 | 3900.00 | 228 | F8 | 3900.00 | | | |
| 232 | F9 | 4495.88 | 233 | F9 | 4495.88 | 234 | F9 | 4495.88 | | | |
| 238 | FA | 5165.49 | 239 | FA | 5165.49 | 240 | FA | 5165.49 | | | |
| 244 | FB | 5890.72 | 245 | FB | 5890.72 | 246 | FB | 5890.72 | | | |
| 250 | FC | 6771.07 | 251 | FC | 6771.07 | 252 | FC | 6771.07 | | | |
| 253 | FD | 7764.20 | 254 | FD | 7764.20 | 255 | FD | 7764.20 | | | |
| 247 | FC | 6771.07 | 248 | FC | 6771.07 | 249 | FC | 6771.07 | | | |
| 241 | FB | 5890.72 | 242 | FB | 5890.72 | 243 | FB | 5890.72 | | | |
| 235 | FA | 5165.49 | 236 | FA | 5165.49 | 237 | FA | 5165.49 | | | |
| 229 | F9 | 4495.88 | 230 | F9 | 4495.88 | 231 | F9 | 4495.88 | | | |
| 223 | F7 | 3476.12 | 224 | F7 | 3476.12 | 225 | F7 | 3476.12 | | | |
| 217 | F5 | 2638.52 | 218 | F5 | 2638.52 | 219 | F5 | 2638.52 | | | |
| 211 | F3 | 2000.94 | 212 | F3 | 2000.94 | 213 | F3 | 2000.94 | | | |
| 205 | ED | 897.59 | 206 | EE | 1031.01 | 207 | EF | 1132.66 | | | |
| 199 | E7 | 402.76 | 200 | E8 | 450.22 | 201 | E9 | 519.13 | | | |

| | | | | | | | | |
|-----|----|--------|-----|----|--------|-----|----|--------|
| 193 | E1 | 176.57 | 194 | E2 | 202.94 | 195 | E3 | 231.48 |
| 187 | DB | 78.85 | 188 | DC | 90.65 | 189 | DD | 104.03 |
| 181 | D5 | 35.35 | 182 | D6 | 40.60 | 183 | D7 | 46.59 |
| 175 | CF | 15.81 | 176 | D0 | 17.67 | 177 | D1 | 20.40 |
| 169 | C9 | 6.94 | 170 | CA | 7.97 | 171 | CB | 9.09 |
| 163 | C3 | 3.05 | 164 | C4 | 3.50 | 165 | C5 | 4.02 |

| OFS | HEX | HV | OFS | HEX | HV | OFS | HEX | HV |
|-----|-----|----------|-----|-----|----------|-----|-----|----------|
| 122 | 25 | * | 121 | 26 | * | 120 | 27 | * |
| 116 | 2B | * | 115 | 2C | -1.43* | 114 | 2D | * |
| 110 | 31 | * | 109 | 32 | -3.34* | 108 | 33 | * |
| 104 | 37 | | 103 | 38 | -7.58 | 102 | 39 | |
| 98 | 3D | | 97 | 3E | -17.44 | 96 | 3F | -20.04 |
| 101 | 3A | -10.08 | 100 | 3B | | 99 | 3C | -13.23 |
| 107 | 34 | -4.41 | 106 | 35 | | 105 | 36 | -5.84 |
| 113 | 2E | -1.91 | 112 | 2F | | 111 | 30 | -2.48 |
| 119 | 28 | -0.76 | 118 | 29 | | 117 | 2A | -1.06 |
| 95 | 40 | -2.01* | 94 | 41 | -2.32* | 93 | 42 | -2.64* |
| 89 | 46 | -4.60* | 88 | 47 | -5.30* | 87 | 48 | -5.96* |
| 83 | 4C | -10.37* | 82 | 4D | -11.90* | 81 | 4E | -13.65* |
| 77 | 52 | -23.24 | 76 | 53 | -26.47 | 75 | 54 | -30.46 |
| 71 | 58 | -51.56 | 70 | 59 | -59.44 | 69 | 5A | -68.30 |
| 65 | 5E | -118.03 | 64 | 5F | -135.39 | 63 | 60 | -151.16 |
| 59 | 64 | -262.60 | 58 | 65 | -301.35 | 57 | 66 | -346.07 |
| 53 | 6A | -588.77 | 52 | 6B | -671.69 | 51 | 6C | -772.04 |
| 47 | 70 | -1305.91 | 46 | 71 | -1505.68 | 45 | 72 | -1730.26 |
| 41 | 74 | -2268.57 | 40 | 74 | -2268.57 | 39 | 74 | -2268.57 |
| 35 | 76 | -2988.05 | 34 | 76 | -2988.05 | 33 | 76 | -2988.05 |
| 29 | 78 | -3844.85 | 28 | 78 | -3844.85 | 27 | 78 | -3844.85 |
| 23 | 79 | -4431.88 | 22 | 79 | -4431.88 | 21 | 79 | -4431.88 |
| 17 | 7A | -5091.10 | 16 | 7A | -5091.10 | 15 | 7A | -5091.10 |
| 11 | 7B | -5806.19 | 10 | 7B | -5806.19 | 9 | 7B | -5806.19 |
| 5 | 7C | -6669.12 | 4 | 7C | -6669.12 | 3 | 7C | -6669.12 |
| 2 | 7D | -7648.35 | 1 | 7D | -7648.35 | 0 | 7D | -7648.35 |
| 8 | 7C | -6669.12 | 7 | 7C | -6669.12 | 6 | 7C | -6669.12 |
| 14 | 7B | -5806.19 | 13 | 7B | -5806.19 | 12 | 7B | -5806.19 |
| 20 | 7A | -5091.10 | 19 | 7A | -5091.10 | 18 | 7A | -5091.10 |
| 26 | 79 | -4431.88 | 25 | 79 | -4431.88 | 24 | 79 | -4431.88 |
| 32 | 77 | -3427.04 | 31 | 77 | -3427.04 | 30 | 77 | -3427.04 |
| 38 | 75 | -2602.55 | 37 | 75 | -2602.55 | 36 | 75 | -2602.55 |
| 44 | 73 | -1978.86 | 43 | 73 | -1978.86 | 42 | 73 | -1978.86 |
| 50 | 6D | -885.79 | 49 | 6E | -1017.17 | 48 | 6F | -1166.87 |
| 56 | 67 | -397.05 | 55 | 68 | -444.39 | 54 | 69 | -512.38 |
| 62 | 61 | -174.31 | 61 | 62 | -200.28 | 60 | 63 | -228.52 |
| 68 | 5B | -77.95 | 67 | 5C | -89.59 | 66 | 5D | -102.79 |
| 74 | 55 | -34.97 | 73 | 56 | -40.12 | 72 | 57 | -46.04 |
| 80 | 4F | -15.65 | 79 | 50 | -17.52 | 78 | 51 | -20.23 |
| 86 | 49 | -6.87 | 85 | 4A | -7.90 | 84 | 4B | -9.04 |
| 92 | 43 | -3.04 | 91 | 44 | -3.49 | 90 | 45 | -4.03 |

NOTES

Where voltage values are left blank, it is only because no calibration data were given for those levels. It is reasonable to suppose that they interpolate smoothly between adjacent calibrated levels.

Asterisks mark voltage levels probably corrupted by switching transients.

Nine descriptors produce this sequence, and they are given in SCSQ_2E.4.1.

SCSQ_2E.3. The PPA Scan

The PPA scan program calculates offsets into its deflection voltage lookup table, given in section SCSQ_2E.6.2. The lookup table has 128 elements, only one polarity, and may consist simply of an identity transformation.

The PPA cycle will concentrate on levels 085-120, which correspond nominally to 0.5 to 5 keV electrons. There are 36 deflection voltage levels in this interval, and they are covered by two staggered scans of 18 levels each. The PPA scan cycle of 36 levels is repeated 2 times in a scan resynchronization interval of 18 major frames.

First column 1 from top to bottom, then column 2 from top to bottom.

| OFS | HV | OFS | HV |
|-----|-------|-----|-------|
| 085 | -589 | 086 | -630 |
| 089 | -771 | 090 | -825 |
| 093 | -1011 | 094 | -1082 |
| 097 | -1325 | 098 | -1417 |
| 101 | -1736 | 102 | -1857 |
| 105 | -2275 | 106 | -2434 |
| 109 | -2981 | 110 | -3190 |
| 113 | -3907 | 114 | -4180 |
| 117 | -5120 | 118 | -5478 |
| 119 | -5861 | 120 | -6271 |
| 115 | -4472 | 116 | -4785 |
| 111 | -3413 | 112 | -3651 |
| 107 | -2604 | 108 | -2786 |
| 103 | -1987 | 104 | -2126 |
| 099 | -1516 | 100 | -1622 |
| 095 | -1157 | 096 | -1238 |
| 091 | -883 | 092 | -945 |
| 087 | -674 | 088 | -721 |

The time profile of each scan is pyramidal, which is to say that the deflection voltage ramps up and then ramps down, so that there are no end-to-end steps. The descriptor element that we call "scan increment" specifies the size of the gaps in an

entire up-down scan. On the way up the step size is two scan increments, and on the way down it is two scan increments, but since the up-scan is interleaved with the down-scan, the overall pitch is one scan increment.

The scans were chosen to comply with the deflection supply slewing limitation of 500 volts/millisecond.

One descriptor produces this sequence, and is given in section SCSQ_2E.4.2.

SCSQ_2E.4. Descriptors

The SCSQ_2E sequence is produced by the following descriptors. The DDEIS descriptors follow one another in a loop, called D2EComp. Individual descriptors may be designated, e.g.: D2EComp-0, D2EComp-1, etc.

SCSQ_2E.4.1. DDEIS SCAN VECTORS

| Sequence Name | -----D2EComp----- | | | | | | | | | |
|--|-------------------|-----|-----|----|-----|-----|-----|----|-----|-----|
| HV Lookup Table | DSHV100.TAB | | | | | | | | | |
| Coordinated PP Descriptor | PP0 | | | | | | | | | |
| MJF's Per Resynch. Interval | 18 | | | | | | | | | |
| Nd | 512 | | | | | | | | | |
| Descriptor Number | 0 | 1 | 2 | 3 | 4 | 5 | 6 | 7 | 8 | |
| Scan Base Level | 127 | 160 | 122 | 95 | 127 | 160 | 122 | 95 | 127 | |
| 0 <= Base <= 255 (internal scale) | | | | | | | | | | |
| Scan Increment | +3 | +3 | -3 | -3 | +3 | +3 | -3 | -3 | 0 | |
| Number of HV Steps Per Scan (DDN's/DSC) | 11 | 32 | 9 | 32 | 11 | 32 | 9 | 32 | 8 | |
| Offset Base (+-Levels) | 0 | 0 | 0 | 0 | 0 | 0 | 0 | 0 | 0 | +32 |
| Offset Increment (+-) | +1 | +1 | -1 | -1 | +1 | +1 | -1 | -1 | -1 | 0 |
| Scans Per Offset Cycle | 3 | 3 | 3 | 3 | 3 | 3 | 3 | 3 | 3 | 1 |
| # Interrupts per Energy Step (BCI's/DDN) | 2 | 2 | 2 | 2 | 2 | 2 | 2 | 2 | 2 | 2 |
| # Interrupts per Accumulation (BCI's/DDC) | 2 | 2 | 2 | 2 | 2 | 2 | 2 | 2 | 2 | 2 |
| Number of Next Scan Descriptor | 1 | 2 | 3 | 4 | 5 | 6 | 7 | 0 | 0 | |
| Number of Next Cycle Descriptor | 1 | 2 | 3 | 4 | 5 | 6 | 7 | 8 | 0 | |
| Sensor Polarity | + | + | - | - | + | + | - | - | - | |

SCSQ_2E.4.2. PPA SCAN VECTOR

| | |
|-------------------|-----|
| Descriptor Number | PP0 |
| Scan Base Level | 85 |
| 0 <= Base <= 127 | |
| Scan Increment | 2 |

| | |
|--------------------------|-------------|
| Number of HV Steps | 18 |
| Per Scan | |
| Offset Base (+-Levels) | 0 |
| Offset Increment (+-) | 1 |
| Scans Per Offset Cycle | 2 |
| # Interrupts per | 128 |
| Energy Step (BCI's/PPN) | |
| # Interrupts per | 128 |
| Accumulation (BCI's/PPC) | |
| Address of Next | PP0 |
| Scan Descriptor | |
| Address of Next | PP0 |
| Cycle Descriptor | |
| Sensor Polarity | (null byte) |

SCSQ_2E.4.3. Related Timing Parameters

In addition to the descriptor variables, there are other parameters that must be managed in order to keep the scan and data sequences coordinated.

In order to assure that the scan sequences stay synchronized to the telemetry sequence, the scan program is resynchronized periodically. For the SCSQ_2E cases, the sequence resynchronization interval is 18 major frames (165.6 seconds). The sequence resynchronization interval F is written to a RAM variable, so that it can be updated from the ground when a change in descriptors causes a change in the resynchronization cycle.

The DDEIS scan program writes each deflection voltage control byte to a table, for telemetry to pick up. The telemetry task takes 64 bytes from the table in each major frame, cycling through the entire 256-byte length of the table in 4 major frames. As the DDEIS scan does not restart each major frame, the write pointer is cycled with the DDEIS scan cycle. The number of bytes in a cycle must be loaded into a RAM variable in order to tell the task when to restart at the beginning of the table. In loop D2EComp, the length of the DDEIS scan cycle is 512, comprised of 6 subscans of 84 each, plus a dwell of 8. The contents of this RAM variable must be updated when a change in descriptors causes a change in the cycle length.

The correct HV lookup table must be used, and is specified by the name of the FID file that describes it.

SCSQ_2E.5. Sequence Resynchronization Interval

In order to assure that the scan sequences stay synchronized to the telemetry sequence, the scan program is resynchronized periodically. The resynchronization interval is chosen so as be seamless. That is, to contain an integral

number of DDEIS scans, an integral number of PPA scans, and an integral number of telemetry frames. Thus this number is acutely dependent upon the length of the scans. For the SCSQ_2E cases, the sequence resynchronization interval is 18 major frames (165.6 seconds). For other scans, the resynchronization interval must be calculated as described in file RESYNCH.INT. The sequence resynchronization interval F is written to a RAM variable, so that it can be updated from the ground when a change in descriptors causes a change in the resynchronization cycle.

SCSQ_2E.6.0. Deflection Level RAM Lookup Tables

To provide flexibility in dealing with the deflection supplies, two RAM tables (one each for the PPA and DDEIS) will be used by the scan program to look up the HV level control bytes. As determined by its descriptors, the scan program calculates a sequence of one-byte table offsets. Instead of feeding this byte directly to the HV supply, the program uses it to address the RAM lookup table, where it finds the HV level control byte in the offset location. The tables must be loaded manually after each instrument turn-on.

SCSQ_2E.6.1. The DSHV100 RAM Lookup Table for the DDEIS Deflection Supply

Table DSHV100.TAB is identical to the lookup table tailored for the SCSQ_0E ModeZero code, but we gain a better sequence by using the Scan2E descriptors. This is intended as a conservative sequence. Thus, the two highest voltage steps are not used and are absent from the table. A rolloff is applied to the high end of the high ranges in order to restrict the magnitude of any single step to a maximum of 1100 v (550 v per side), when the step size is 6 or less. To provide space for the rolloff, the high ranges are given 96 slots each. Designating the ranges by H and L, and the polarity of the particle detected by + and -, the table is allocated, in order, as shown below:

| Label | Sign Bit | Range Bit | Steps |
|-------------|----------|-----------|-----------|
| H- | 0 | 1 | 96 steps |
| L- | 0 | 0 | 28 steps |
| L+ | 1 | 0 | 36 steps |
| H+ | 1 | 1 | 96 steps |
| Total Table | | | 256 steps |

The L- segment of the table is shorter than L+, because there is a -2 V grid in front of the electron channeltron to suppress secondaries. This also acts as a retarding potential, rejecting electrons of energy below 2 eV. With analyzer constant of 7, this corresponds to an analyzer voltage of A-B = 4/7 V, below which there is no interesting data.

A command byte has negative polarity if MSB=1, and yields deflection voltages that analyze for positive particles. This follows because side A is connected to the outer plate.

A listing of the entire table can be found in file DSHV100.TAB.

SCSQ_2E.6.2. The PPA HV Level RAM Lookup Table

The HV level RAM lookup table for the PPA supplies may be as simple as a linear sequence running from 0 at offset 0 to 127 at offset 127. Of course, a table is not needed to create an identity operation such as this, but it offers flexibility in case the power supply characteristics change.

SCSQ_2E.7.0. Available Deflection Voltage Values

The deflection voltage supplies are expected to run from + or - 0.1 to + or - 5,000 V for the DDEIS, and from - 1.9 to - 10,000 V for the PPA. The DDEIS deflection supply has two polarities, and two ranges, from about 0.1 to 10 V, and 1 to 5000 V. Actual voltage values are given in file DFLSV001.TAB based on calibration data from the SN001 supplies taken at ambient temperature, Sept-Oct, 1992.

The energy/voltage conversion ratios are 7.07 for the DDEIS and 0.83 for the PPA, in units of eV/V.

DSHV100.0. The DSHV100.TAB RAM Lookup Table for the DDEIS
Deflection Supply

The table given below is tailored for the ModeZero code, using ScanOE descriptors, and can be used by similar descriptors. This is intended as a failsafe mode. Thus, the two highest voltage steps are not used and are absent from the table. A rolloff is applied to the high end of the high ranges in order to restrict the magnitude of any single step to a maximum of 1100 v (550 v per side), when the step size is 6 or less. To provide space for the rolloff, the high ranges are given 96 slots each. Designating the ranges by H and L, and the polarity of the particle detected by + and -, the table is allocated, in order, as shown below:

| Label | Sign Bit | Range Bit | Steps |
|-------------|----------|-----------|-----------|
| H- | 0 | 1 | 96 steps |
| L- | 0 | 0 | 28 steps |
| L+ | 1 | 0 | 36 steps |
| H+ | 1 | 1 | 96 steps |
| Total Table | | | 256 steps |

The L- segment of the table is shorter than L+, because there is a -2 V grid in front of the electron channeltron to suppress secondaries. This also acts as a retarding potential, rejecting electrons of energy below 2 eV. With analyzer constant of 7, this corresponds to an analyzer voltage of A-B = 4/7 V, below which there is no interesting data.

A command byte has negative polarity if MSB=1, and yields deflection voltages that analyze for positive particles. This follows because side A is connected to the outer plate.

The high voltage values are based on calibration data from the SN001 supplies taken at ambient temperature, Sept-Oct, 1992.

| Decim. Offset | Pos Neg | Range Select | Level | Control HexByte | HV A-B | Log ABS (HV) |
|------------------|------------|-----------------|-------|--------------------|-----------|-----------------|
| 0 | 0 | 1 | 61 | 7D | -7648.35 | 3.88 |
| 1 | 0 | 1 | 61 | 7D | -7648.35 | 3.88 |
| 2 | 0 | 1 | 61 | 7D | -7648.35 | 3.88 |
| 3 | 0 | 1 | 60 | 7C | -6669.12 | 3.82 |
| 4 | 0 | 1 | 60 | 7C | -6669.12 | 3.82 |
| 5 | 0 | 1 | 60 | 7C | -6669.12 | 3.82 |
| 6 | 0 | 1 | 60 | 7C | -6669.12 | 3.82 |
| 7 | 0 | 1 | 60 | 7C | -6669.12 | 3.82 |
| 8 | 0 | 1 | 60 | 7C | -6669.12 | 3.82 |
| 9 | 0 | 1 | 59 | 7B | -5806.19 | 3.76 |
| 10 | 0 | 1 | 59 | 7B | -5806.19 | 3.76 |
| 11 | 0 | 1 | 59 | 7B | -5806.19 | 3.76 |
| 12 | 0 | 1 | 59 | 7B | -5806.19 | 3.76 |
| 13 | 0 | 1 | 59 | 7B | -5806.19 | 3.76 |
| 14 | 0 | 1 | 59 | 7B | -5806.19 | 3.76 |
| 15 | 0 | 1 | 58 | 7A | -5091.1 | 3.71 |
| 16 | 0 | 1 | 58 | 7A | -5091.1 | 3.71 |
| 17 | 0 | 1 | 58 | 7A | -5091.1 | 3.71 |
| 18 | 0 | 1 | 58 | 7A | -5091.1 | 3.71 |
| 19 | 0 | 1 | 58 | 7A | -5091.1 | 3.71 |
| 20 | 0 | 1 | 58 | 7A | -5091.1 | 3.71 |
| 21 | 0 | 1 | 57 | 79 | -4431.88 | 3.65 |
| 22 | 0 | 1 | 57 | 79 | -4431.88 | 3.65 |
| 23 | 0 | 1 | 57 | 79 | -4431.88 | 3.65 |
| 24 | 0 | 1 | 57 | 79 | -4431.88 | 3.65 |
| 25 | 0 | 1 | 57 | 79 | -4431.88 | 3.65 |
| 26 | 0 | 1 | 57 | 79 | -4431.88 | 3.65 |
| 27 | 0 | 1 | 56 | 78 | -3844.85 | 3.58 |
| 28 | 0 | 1 | 56 | 78 | -3844.85 | 3.58 |
| 29 | 0 | 1 | 56 | 78 | -3844.85 | 3.58 |
| 30 | 0 | 1 | 55 | 77 | -3427.04 | 3.53 |
| 31 | 0 | 1 | 55 | 77 | -3427.04 | 3.53 |
| 32 | 0 | 1 | 55 | 77 | -3427.04 | 3.53 |
| 33 | 0 | 1 | 54 | 76 | -2988.05 | 3.48 |
| 34 | 0 | 1 | 54 | 76 | -2988.05 | 3.48 |
| 35 | 0 | 1 | 54 | 76 | -2988.05 | 3.48 |
| 36 | 0 | 1 | 53 | 75 | -2602.55 | 3.42 |
| 37 | 0 | 1 | 53 | 75 | -2602.55 | 3.42 |
| 38 | 0 | 1 | 53 | 75 | -2602.55 | 3.42 |
| 39 | 0 | 1 | 52 | 74 | -2268.57 | 3.36 |
| 40 | 0 | 1 | 52 | 74 | -2268.57 | 3.36 |
| 41 | 0 | 1 | 52 | 74 | -2268.57 | 3.36 |
| 42 | 0 | 1 | 51 | 73 | -1978.86 | 3.30 |
| 43 | 0 | 1 | 51 | 73 | -1978.86 | 3.30 |
| 44 | 0 | 1 | 51 | 73 | -1978.86 | 3.30 |
| 45 | 0 | 1 | 50 | 72 | -1730.26 | 3.24 |
| 46 | 0 | 1 | 49 | 71 | -1505.68 | 3.18 |
| 47 | 0 | 1 | 48 | 70 | -1305.91 | 3.12 |

| Decim. Offset | Pos Neg | Range Select | Level | Control HexByte | HV A-B | Log ABS (HV) |
|------------------|------------|-----------------|-------|--------------------|-----------|-----------------|
| 48 | 0 | 1 | 47 | 6F | -1166.87 | 3.07 |
| 49 | 0 | 1 | 46 | 6E | -1017.17 | 3.01 |
| 50 | 0 | 1 | 45 | 6D | -885.79 | 2.95 |
| 51 | 0 | 1 | 44 | 6C | -772.04 | 2.89 |
| 52 | 0 | 1 | 43 | 6B | -671.69 | 2.83 |
| 53 | 0 | 1 | 42 | 6A | -588.77 | 2.77 |
| 54 | 0 | 1 | 41 | 69 | -512.38 | 2.71 |
| 55 | 0 | 1 | 40 | 68 | -444.39 | 2.65 |
| 56 | 0 | 1 | 39 | 67 | -397.05 | 2.60 |
| 57 | 0 | 1 | 38 | 66 | -346.07 | 2.54 |
| 58 | 0 | 1 | 37 | 65 | -301.35 | 2.48 |
| 59 | 0 | 1 | 36 | 64 | -262.60 | 2.42 |
| 60 | 0 | 1 | 35 | 63 | -228.52 | 2.36 |
| 61 | 0 | 1 | 34 | 62 | -200.28 | 2.30 |
| 62 | 0 | 1 | 33 | 61 | -174.31 | 2.24 |
| 63 | 0 | 1 | 32 | 60 | -151.16 | 2.18 |
| 64 | 0 | 1 | 31 | 5F | -135.39 | 2.13 |
| 65 | 0 | 1 | 30 | 5E | -118.03 | 2.07 |
| 66 | 0 | 1 | 29 | 5D | -102.79 | 2.01 |
| 67 | 0 | 1 | 28 | 5C | -89.59 | 1.95 |
| 68 | 0 | 1 | 27 | 5B | -77.95 | 1.89 |
| 69 | 0 | 1 | 26 | 5A | -68.30 | 1.83 |
| 70 | 0 | 1 | 25 | 59 | -59.44 | 1.77 |
| 71 | 0 | 1 | 24 | 58 | -51.56 | 1.71 |
| 72 | 0 | 1 | 23 | 57 | -46.04 | 1.66 |
| 73 | 0 | 1 | 22 | 56 | -40.12 | 1.60 |
| 74 | 0 | 1 | 21 | 55 | -34.97 | 1.54 |
| 75 | 0 | 1 | 20 | 54 | -30.46 | 1.48 |
| 76 | 0 | 1 | 19 | 53 | -26.47 | 1.42 |
| 77 | 0 | 1 | 18 | 52 | -23.24 | 1.37 |
| 78 | 0 | 1 | 17 | 51 | -20.23 | 1.31 |
| 79 | 0 | 1 | 16 | 50 | -17.52 | 1.24 |
| 80 | 0 | 1 | 15 | 4F | -15.65 | 1.19 |
| 81 | 0 | 1 | 14 | 4E | -13.65 | 1.14 |
| 82 | 0 | 1 | 13 | 4D | -11.90 | 1.08 |
| 83 | 0 | 1 | 12 | 4C | -10.37 | 1.02 |
| 84 | 0 | 1 | 11 | 4B | -9.04 | 0.956 |
| 85 | 0 | 1 | 10 | 4A | -7.90 | 0.898 |
| 86 | 0 | 1 | 9 | 49 | -6.87 | 0.837 |
| 87 | 0 | 1 | 8 | 48 | -5.96 | 0.775 |
| 88 | 0 | 1 | 7 | 47 | -5.30 | 0.724 |
| 89 | 0 | 1 | 6 | 46 | -4.60 | 0.663 |
| 90 | 0 | 1 | 5 | 45 | -4.03 | 0.605 |
| 91 | 0 | 1 | 4 | 44 | -3.49 | 0.543 |
| 92 | 0 | 1 | 3 | 43 | -3.04 | 0.483 |
| 93 | 0 | 1 | 2 | 42 | -2.64 | 0.422 |
| 94 | 0 | 1 | 1 | 41 | -2.32 | 0.365 |
| 95 | 0 | 1 | 0 | 40 | -2.01 | 0.303 |

| Decim. Offset | Pos Neg | Range Select | Level | Control HexByte | HV A-B | Log ABS(HV) |
|------------------|------------|-----------------|-------|--------------------|-----------|----------------|
| 96 | 0 | 0 | 63 | 3F | -20.04 | 1.30 |
| 97 | 0 | 0 | 62 | 3E | -17.44 | 1.24 |
| 98 | 0 | 0 | 61 | 3D | | |
| 99 | 0 | 0 | 60 | 3C | -13.23 | 1.12 |
| 100 | 0 | 0 | 59 | 3B | | |
| 101 | 0 | 0 | 58 | 3A | -10.08 | 1.00 |
| 102 | 0 | 0 | 57 | 39 | | |
| 103 | 0 | 0 | 56 | 38 | -7.58 | 0.880 |
| 104 | 0 | 0 | 55 | 37 | | |
| 105 | 0 | 0 | 54 | 36 | -5.84 | 0.766 |
| 106 | 0 | 0 | 53 | 35 | | |
| 107 | 0 | 0 | 52 | 34 | -4.41 | 0.644 |
| 108 | 0 | 0 | 51 | 33 | | |
| 109 | 0 | 0 | 50 | 32 | -3.34 | 0.524 |
| 110 | 0 | 0 | 49 | 31 | | |
| 111 | 0 | 0 | 48 | 30 | -2.48 | 0.394 |
| 112 | 0 | 0 | 47 | 2F | | |
| 113 | 0 | 0 | 46 | 2E | -1.91 | 0.281 |
| 114 | 0 | 0 | 45 | 2D | | |
| 115 | 0 | 0 | 44 | 2C | -1.43 | 0.155 |
| 116 | 0 | 0 | 43 | 2B | | |
| 117 | 0 | 0 | 42 | 2A | -1.06 | 0.025 |
| 118 | 0 | 0 | 41 | 29 | | |
| 119 | 0 | 0 | 40 | 28 | -0.76 | -0.12 |
| 120 | 0 | 0 | 39 | 27 | | |
| 121 | 0 | 0 | 38 | 26 | | |
| 122 | 0 | 0 | 37 | 25 | | |
| 123 | 0 | 0 | 36 | 24 | -0.39 | -0.41 |

| Decim. Offset | Pos Neg | Range Select | Level | Control HexByte | HV A-B | Log ABS(HV) |
|------------------|------------|-----------------|-------|--------------------|-----------|----------------|
| 124 | 1 | 0 | 28 | 9C | 0.31 | -0.51 |
| 125 | 1 | 0 | 29 | 9D | | |
| 126 | 1 | 0 | 30 | 9E | | |
| 127 | 1 | 0 | 31 | 9F | | |
| 128 | 1 | 0 | 32 | A0 | 0.42 | -0.38 |
| 129 | 1 | 0 | 33 | A1 | | |
| 130 | 1 | 0 | 34 | A2 | | |
| 131 | 1 | 0 | 35 | A3 | | |
| 132 | 1 | 0 | 36 | A4 | 0.65 | -0.19 |
| 133 | 1 | 0 | 37 | A5 | | |
| 134 | 1 | 0 | 38 | A6 | | |
| 135 | 1 | 0 | 39 | A7 | | |
| 136 | 1 | 0 | 40 | A8 | 1.01 | 0.004 |
| 137 | 1 | 0 | 41 | A9 | | |
| 138 | 1 | 0 | 42 | AA | 1.31 | 0.117 |
| 139 | 1 | 0 | 43 | AB | | |
| 140 | 1 | 0 | 44 | AC | 1.70 | 0.230 |
| 141 | 1 | 0 | 45 | AD | | |
| 142 | 1 | 0 | 46 | AE | 2.19 | 0.340 |
| 143 | 1 | 0 | 47 | AF | | |
| 144 | 1 | 0 | 48 | B0 | 2.76 | 0.441 |
| 145 | 1 | 0 | 49 | B1 | | |
| 146 | 1 | 0 | 50 | B2 | 3.63 | 0.560 |
| 147 | 1 | 0 | 51 | B3 | | |
| 148 | 1 | 0 | 52 | B4 | 4.73 | 0.675 |
| 149 | 1 | 0 | 53 | B5 | | |
| 150 | 1 | 0 | 54 | B6 | | |
| 151 | 1 | 0 | 55 | B7 | | |
| 152 | 1 | 0 | 56 | B8 | 7.43 | 0.871 |
| 153 | 1 | 0 | 57 | B9 | | |
| 154 | 1 | 0 | 58 | BA | 10.46 | 1.02 |
| 155 | 1 | 0 | 59 | BB | | |
| 156 | 1 | 0 | 60 | BC | 13.68 | 1.14 |
| 157 | 1 | 0 | 61 | BD | | |
| 158 | 1 | 0 | 62 | BE | 17.98 | 1.25 |
| 159 | 1 | 0 | 63 | BF | 20.62 | 1.31 |

| Decim. Offset | Pos Neg | Range Select | Level | Control HexByte | HV A-B | Log ABS(HV) |
|------------------|------------|-----------------|-------|--------------------|-----------|----------------|
| 160 | 1 | 1 | 0 | C0 | 2.02 | 0.305 |
| 161 | 1 | 1 | 1 | C1 | 2.32 | 0.365 |
| 162 | 1 | 1 | 2 | C2 | 2.68 | 0.428 |
| 163 | 1 | 1 | 3 | C3 | 3.05 | 0.484 |
| 164 | 1 | 1 | 4 | C4 | 3.50 | 0.544 |
| 165 | 1 | 1 | 5 | C5 | 4.02 | 0.604 |
| 166 | 1 | 1 | 6 | C6 | 4.64 | 0.667 |
| 167 | 1 | 1 | 7 | C7 | 5.35 | 0.728 |
| 168 | 1 | 1 | 8 | C8 | 5.99 | 0.777 |
| 169 | 1 | 1 | 9 | C9 | 6.94 | 0.841 |
| 170 | 1 | 1 | 10 | CA | 7.97 | 0.901 |
| 171 | 1 | 1 | 11 | CB | 9.09 | 0.959 |
| 172 | 1 | 1 | 12 | CC | 10.45 | 1.02 |
| 173 | 1 | 1 | 13 | CD | 11.99 | 1.08 |
| 174 | 1 | 1 | 14 | CE | 13.77 | 1.14 |
| 175 | 1 | 1 | 15 | CF | 15.81 | 1.20 |
| 176 | 1 | 1 | 16 | D0 | 17.67 | 1.25 |
| 177 | 1 | 1 | 17 | D1 | 20.40 | 1.31 |
| 178 | 1 | 1 | 18 | D2 | 23.47 | 1.37 |
| 179 | 1 | 1 | 19 | D3 | 26.79 | 1.43 |
| 180 | 1 | 1 | 20 | D4 | 30.82 | 1.49 |
| 181 | 1 | 1 | 21 | D5 | 35.35 | 1.55 |
| 182 | 1 | 1 | 22 | D6 | 40.60 | 1.61 |
| 183 | 1 | 1 | 23 | D7 | 46.59 | 1.67 |
| 184 | 1 | 1 | 24 | D8 | 52.14 | 1.72 |
| 185 | 1 | 1 | 25 | D9 | 60.12 | 1.78 |
| 186 | 1 | 1 | 26 | DA | 69.11 | 1.84 |
| 187 | 1 | 1 | 27 | DB | 78.85 | 1.90 |
| 188 | 1 | 1 | 28 | DC | 90.65 | 1.96 |
| 189 | 1 | 1 | 29 | DD | 104.03 | 2.02 |
| 190 | 1 | 1 | 30 | DE | 119.53 | 2.08 |
| 191 | 1 | 1 | 31 | DF | 137.11 | 2.14 |
| 192 | 1 | 1 | 32 | E0 | 153.13 | 2.19 |
| 193 | 1 | 1 | 33 | E1 | 176.57 | 2.25 |
| 194 | 1 | 1 | 34 | E2 | 202.94 | 2.31 |
| 195 | 1 | 1 | 35 | E3 | 231.48 | 2.36 |
| 196 | 1 | 1 | 36 | E4 | 266.13 | 2.43 |
| 197 | 1 | 1 | 37 | E5 | 305.29 | 2.48 |
| 198 | 1 | 1 | 38 | E6 | 350.68 | 2.54 |
| 199 | 1 | 1 | 39 | E7 | 402.76 | 2.61 |
| 200 | 1 | 1 | 40 | E8 | 450.22 | 2.65 |
| 201 | 1 | 1 | 41 | E9 | 519.13 | 2.72 |
| 202 | 1 | 1 | 42 | EA | 596.60 | 2.78 |
| 203 | 1 | 1 | 43 | EB | 680.57 | 2.83 |
| 204 | 1 | 1 | 44 | EC | 782.43 | 2.89 |
| 205 | 1 | 1 | 45 | ED | 897.59 | 2.95 |
| 206 | 1 | 1 | 46 | EE | 1031.01 | 3.01 |
| 207 | 1 | 1 | 47 | EF | 1132.66 | 3.05 |

| Decim. Offset | Pos Neg | Range Select | Level | Control HexByte | HV A-B | Log ABS(HV) |
|------------------|------------|-----------------|-------|--------------------|-----------|----------------|
| 208 | 1 | 1 | 48 | F0 | 1323.89 | 3.12 |
| 209 | 1 | 1 | 49 | F1 | 1526.38 | 3.18 |
| 210 | 1 | 1 | 50 | F2 | 1754.10 | 3.24 |
| 211 | 1 | 1 | 51 | F3 | 2000.94 | 3.30 |
| 212 | 1 | 1 | 51 | F3 | 2000.94 | 3.30 |
| 213 | 1 | 1 | 51 | F3 | 2000.94 | 3.30 |
| 214 | 1 | 1 | 52 | F4 | 2300.28 | 3.36 |
| 215 | 1 | 1 | 52 | F4 | 2300.28 | 3.36 |
| 216 | 1 | 1 | 52 | F4 | 2300.28 | 3.36 |
| 217 | 1 | 1 | 53 | F5 | 2638.52 | 3.42 |
| 218 | 1 | 1 | 53 | F5 | 2638.52 | 3.42 |
| 219 | 1 | 1 | 53 | F5 | 2638.52 | 3.42 |
| 220 | 1 | 1 | 54 | F6 | 3030.62 | 3.48 |
| 221 | 1 | 1 | 54 | F6 | 3030.62 | 3.48 |
| 222 | 1 | 1 | 54 | F6 | 3030.62 | 3.48 |
| 223 | 1 | 1 | 55 | F7 | 3476.12 | 3.54 |
| 224 | 1 | 1 | 55 | F7 | 3476.12 | 3.54 |
| 225 | 1 | 1 | 55 | F7 | 3476.12 | 3.54 |
| 226 | 1 | 1 | 56 | F8 | 3900.00 | 3.59 |
| 227 | 1 | 1 | 56 | F8 | 3900.00 | 3.59 |
| 228 | 1 | 1 | 56 | F8 | 3900.00 | 3.59 |
| 229 | 1 | 1 | 57 | F9 | 4495.88 | 3.65 |
| 230 | 1 | 1 | 57 | F9 | 4495.88 | 3.65 |
| 231 | 1 | 1 | 57 | F9 | 4495.88 | 3.65 |
| 232 | 1 | 1 | 57 | F9 | 4495.88 | 3.65 |
| 233 | 1 | 1 | 57 | F9 | 4495.88 | 3.65 |
| 234 | 1 | 1 | 57 | F9 | 4495.88 | 3.65 |
| 235 | 1 | 1 | 58 | FA | 5165.49 | 3.71 |
| 236 | 1 | 1 | 58 | FA | 5165.49 | 3.71 |
| 237 | 1 | 1 | 58 | FA | 5165.49 | 3.71 |
| 238 | 1 | 1 | 58 | FA | 5165.49 | 3.71 |
| 239 | 1 | 1 | 58 | FA | 5165.49 | 3.71 |
| 240 | 1 | 1 | 58 | FA | 5165.49 | 3.71 |
| 241 | 1 | 1 | 59 | FB | 5890.72 | 3.77 |
| 242 | 1 | 1 | 59 | FB | 5890.72 | 3.77 |
| 243 | 1 | 1 | 59 | FB | 5890.72 | 3.77 |
| 244 | 1 | 1 | 59 | FB | 5890.72 | 3.77 |
| 245 | 1 | 1 | 59 | FB | 5890.72 | 3.77 |
| 246 | 1 | 1 | 59 | FB | 5890.72 | 3.77 |
| 247 | 1 | 1 | 60 | FC | 6771.07 | 3.83 |
| 248 | 1 | 1 | 60 | FC | 6771.07 | 3.83 |
| 249 | 1 | 1 | 60 | FC | 6771.07 | 3.83 |
| 250 | 1 | 1 | 60 | FC | 6771.07 | 3.83 |
| 251 | 1 | 1 | 60 | FC | 6771.07 | 3.83 |
| 252 | 1 | 1 | 60 | FC | 6771.07 | 3.83 |
| 253 | 1 | 1 | 61 | FD | 7764.20 | 3.89 |
| 254 | 1 | 1 | 61 | FD | 7764.20 | 3.89 |
| 255 | 1 | 1 | 61 | FD | 7764.20 | 3.89 |

DFLSV001.0. Deflection Supply Voltage Tables, SN001

The following are the voltages available with our power supplies.

DFLSV001.1. DDEIS Deflection Supply

The following table is based on calibration data from the SN001 supplies taken at ambient temperature, Sept-Oct, 1992.

A command byte has negative polarity if MSB=1, and yields deflection voltages that analyze for positive particles. This follows because side A is connected to the outer plate. Note that the step size on the log(HV) scale approximates a uniform 0.06 across both ranges. This can be compared with the analyzer resolution, given by $\log((E+\Delta E)/E) = \log(1.08) = 0.033$.

Positive Polarity, Low Range

| Pos | Range | | Control | HV | Log |
|-----|--------|-------|---------|--------|---------|
| Neg | Select | Level | HexByte | A-B | ABS(HV) |
| 0 | 0 | 63 | 3F | -20.04 | 1.30 |
| 0 | 0 | 62 | 3E | -17.44 | 1.24 |
| 0 | 0 | 61 | 3D | | |
| 0 | 0 | 60 | 3C | -13.23 | 1.12 |
| 0 | 0 | 59 | 3B | | |
| 0 | 0 | 58 | 3A | -10.08 | 1.00 |
| 0 | 0 | 57 | 39 | | |
| 0 | 0 | 56 | 38 | -7.58 | 0.880 |
| 0 | 0 | 55 | 37 | | |
| 0 | 0 | 54 | 36 | -5.84 | 0.766 |
| 0 | 0 | 53 | 35 | | |
| 0 | 0 | 52 | 34 | -4.41 | 0.644 |
| 0 | 0 | 51 | 33 | | |
| 0 | 0 | 50 | 32 | -3.34 | 0.524 |
| 0 | 0 | 49 | 31 | | |
| 0 | 0 | 48 | 30 | -2.48 | 0.394 |
| 0 | 0 | 47 | 2F | | |
| 0 | 0 | 46 | 2E | -1.91 | 0.281 |
| 0 | 0 | 45 | 2D | | |
| 0 | 0 | 44 | 2C | -1.43 | 0.155 |
| 0 | 0 | 43 | 2B | | |
| 0 | 0 | 42 | 2A | -1.06 | 0.025 |
| 0 | 0 | 41 | 29 | | |
| 0 | 0 | 40 | 28 | -0.76 | -0.12 |
| 0 | 0 | 39 | 27 | | |
| 0 | 0 | 38 | 26 | | |
| 0 | 0 | 37 | 25 | | |
| 0 | 0 | 36 | 24 | -0.39 | -0.41 |
| 0 | 0 | 35 | 23 | | |
| 0 | 0 | 34 | 22 | | |
| 0 | 0 | 33 | 21 | | |
| 0 | 0 | 32 | 20 | -0.17 | -0.77 |
| 0 | 0 | 31 | 1F | | |
| 0 | 0 | 30 | 1E | | |
| 0 | 0 | 29 | 1D | | |
| 0 | 0 | 28 | 1C | -0.07 | -1.2 |
| 0 | 0 | 27 | 1B | | |
| 0 | 0 | 26 | 1A | | |
| 0 | 0 | 25 | 19 | | |
| 0 | 0 | 24 | 18 | | |
| 0 | 0 | 23 | 17 | | |
| 0 | 0 | 22 | 16 | | |
| 0 | 0 | 21 | 15 | | |
| 0 | 0 | 20 | 14 | 0.05 | -1.3 |
| 0 | 0 | 19 | 13 | | |
| 0 | 0 | 18 | 12 | | |
| 0 | 0 | 17 | 11 | | |
| 0 | 0 | 16 | 10 | | |
| 0 | 0 | 15 | 0F | | |

| | | | |
|---|---|----|-----------------|
| 0 | 0 | 14 | 0E |
| 0 | 0 | 13 | 0D |
| 0 | 0 | 12 | 0C |
| 0 | 0 | 11 | 0B |
| 0 | 0 | 10 | 0A |
| 0 | 0 | 9 | 09 |
| 0 | 0 | 8 | 08 |
| 0 | 0 | 7 | 07 |
| 0 | 0 | 6 | 06 |
| 0 | 0 | 5 | 05 |
| 0 | 0 | 4 | 04 |
| 0 | 0 | 3 | 03 |
| 0 | 0 | 2 | 02 |
| 0 | 0 | 1 | 01 |
| 0 | 0 | 00 | 0.12 -0.92 |

Positive Polarity, High Range

| Pos | Neg | Range Select | Level | Control HexByte | HV A-B | Log ABS(HV) |
|-----|-----|--------------|-------|-----------------|-----------|-------------|
| 0 | 1 | 63 | | 7F | -10058.06 | 4.00 |
| 0 | 1 | 62 | | 7E | -8773.63 | 3.94 |
| 0 | 1 | 61 | | 7D | -7648.35 | 3.88 |
| 0 | 1 | 60 | | 7C | -6669.12 | 3.82 |
| 0 | 1 | 59 | | 7B | -5806.19 | 3.76 |
| 0 | 1 | 58 | | 7A | -5091.1 | 3.71 |
| 0 | 1 | 57 | | 79 | -4431.88 | 3.65 |
| 0 | 1 | 56 | | 78 | -3844.85 | 3.58 |
| 0 | 1 | 55 | | 77 | -3427.04 | 3.53 |
| 0 | 1 | 54 | | 76 | -2988.05 | 3.48 |
| 0 | 1 | 53 | | 75 | -2602.55 | 3.42 |
| 0 | 1 | 52 | | 74 | -2268.57 | 3.36 |
| 0 | 1 | 51 | | 73 | -1978.86 | 3.30 |
| 0 | 1 | 50 | | 72 | -1730.26 | 3.24 |
| 0 | 1 | 49 | | 71 | -1505.68 | 3.18 |
| 0 | 1 | 48 | | 70 | -1305.91 | 3.12 |
| 0 | 1 | 47 | | 6F | -1166.87 | 3.07 |
| 0 | 1 | 46 | | 6E | -1017.17 | 3.01 |
| 0 | 1 | 45 | | 6D | -885.79 | 2.95 |
| 0 | 1 | 44 | | 6C | -772.04 | 2.89 |
| 0 | 1 | 43 | | 6B | -671.69 | 2.83 |
| 0 | 1 | 42 | | 6A | -588.77 | 2.77 |
| 0 | 1 | 41 | | 69 | -512.38 | 2.71 |
| 0 | 1 | 40 | | 68 | -444.39 | 2.65 |
| 0 | 1 | 39 | | 67 | -397.05 | 2.60 |
| 0 | 1 | 38 | | 66 | -346.07 | 2.54 |
| 0 | 1 | 37 | | 65 | -301.35 | 2.48 |
| 0 | 1 | 36 | | 64 | -262.60 | 2.42 |
| 0 | 1 | 35 | | 63 | -228.52 | 2.36 |
| 0 | 1 | 34 | | 62 | -200.28 | 2.30 |
| 0 | 1 | 33 | | 61 | -174.31 | 2.24 |
| 0 | 1 | 32 | | 60 | -151.16 | 2.18 |
| 0 | 1 | 31 | | 5F | -135.39 | 2.13 |
| 0 | 1 | 30 | | 5E | -118.03 | 2.07 |
| 0 | 1 | 29 | | 5D | -102.79 | 2.01 |
| 0 | 1 | 28 | | 5C | -89.59 | 1.95 |
| 0 | 1 | 27 | | 5B | -77.95 | 1.89 |
| 0 | 1 | 26 | | 5A | -68.30 | 1.83 |
| 0 | 1 | 25 | | 59 | -59.44 | 1.77 |
| 0 | 1 | 24 | | 58 | -51.56 | 1.71 |
| 0 | 1 | 23 | | 57 | -46.04 | 1.66 |
| 0 | 1 | 22 | | 56 | -40.12 | 1.60 |
| 0 | 1 | 21 | | 55 | -34.97 | 1.54 |
| 0 | 1 | 20 | | 54 | -30.46 | 1.48 |
| 0 | 1 | 19 | | 53 | -26.47 | 1.42 |
| 0 | 1 | 18 | | 52 | -23.24 | 1.37 |
| 0 | 1 | 17 | | 51 | -20.23 | 1.31 |
| 0 | 1 | 16 | | 50 | -17.52 | 1.24 |
| 0 | 1 | 15 | | 4F | -15.65 | 1.19 |

| | | | | | |
|---|---|----|----|--------|-------|
| 0 | 1 | 14 | 4E | -13.65 | 1.14 |
| 0 | 1 | 13 | 4D | -11.90 | 1.08 |
| 0 | 1 | 12 | 4C | -10.37 | 1.02 |
| 0 | 1 | 11 | 4B | -9.04 | 0.956 |
| 0 | 1 | 10 | 4A | -7.90 | 0.898 |
| 0 | 1 | 9 | 49 | -6.87 | 0.837 |
| 0 | 1 | 8 | 48 | -5.96 | 0.775 |
| 0 | 1 | 7 | 47 | -5.30 | 0.724 |
| 0 | 1 | 6 | 46 | -4.60 | 0.663 |
| 0 | 1 | 5 | 45 | -4.03 | 0.605 |
| 0 | 1 | 4 | 44 | -3.49 | 0.543 |
| 0 | 1 | 3 | 43 | -3.04 | 0.483 |
| 0 | 1 | 2 | 42 | -2.64 | 0.422 |
| 0 | 1 | 1 | 41 | -2.32 | 0.365 |
| 0 | 1 | 0 | 40 | -2.01 | 0.303 |

Negative Polarity, High Range

| Pos | Range | | Control | HV | Log |
|-----|--------|-------|---------|---------|---------|
| Neg | Select | Level | HexByte | A-B | ABS(HV) |
| 1 | 1 | 0 | C0 | 2.02 | 0.305 |
| 1 | 1 | 1 | C1 | 2.32 | 0.365 |
| 1 | 1 | 2 | C2 | 2.68 | 0.428 |
| 1 | 1 | 3 | C3 | 3.05 | 0.484 |
| 1 | 1 | 4 | C4 | 3.50 | 0.544 |
| 1 | 1 | 5 | C5 | 4.02 | 0.604 |
| 1 | 1 | 6 | C6 | 4.64 | 0.667 |
| 1 | 1 | 7 | C7 | 5.35 | 0.728 |
| 1 | 1 | 8 | C8 | 5.99 | 0.777 |
| 1 | 1 | 9 | C9 | 6.94 | 0.841 |
| 1 | 1 | 10 | CA | 7.97 | 0.901 |
| 1 | 1 | 11 | CB | 9.09 | 0.959 |
| 1 | 1 | 12 | CC | 10.45 | 1.02 |
| 1 | 1 | 13 | CD | 11.99 | 1.08 |
| 1 | 1 | 14 | CE | 13.77 | 1.14 |
| 1 | 1 | 15 | CF | 15.81 | 1.20 |
| 1 | 1 | 16 | D0 | 17.67 | 1.25 |
| 1 | 1 | 17 | D1 | 20.40 | 1.31 |
| 1 | 1 | 18 | D2 | 23.47 | 1.37 |
| 1 | 1 | 19 | D3 | 26.79 | 1.43 |
| 1 | 1 | 20 | D4 | 30.82 | 1.49 |
| 1 | 1 | 21 | D5 | 35.35 | 1.55 |
| 1 | 1 | 22 | D6 | 40.60 | 1.61 |
| 1 | 1 | 23 | D7 | 46.59 | 1.67 |
| 1 | 1 | 24 | D8 | 52.14 | 1.72 |
| 1 | 1 | 25 | D9 | 60.12 | 1.78 |
| 1 | 1 | 26 | DA | 69.11 | 1.84 |
| 1 | 1 | 27 | DB | 78.85 | 1.90 |
| 1 | 1 | 28 | DC | 90.65 | 1.96 |
| 1 | 1 | 29 | DD | 104.03 | 2.02 |
| 1 | 1 | 30 | DE | 110.53 | 2.04 |
| 1 | 1 | 31 | DF | 137.11 | 2.14 |
| 1 | 1 | 32 | E0 | 153.13 | 2.19 |
| 1 | 1 | 33 | E1 | 176.57 | 2.25 |
| 1 | 1 | 34 | E2 | 202.94 | 2.31 |
| 1 | 1 | 35 | E3 | 231.48 | 2.36 |
| 1 | 1 | 36 | E4 | 266.13 | 2.43 |
| 1 | 1 | 37 | E5 | 305.29 | 2.48 |
| 1 | 1 | 38 | E6 | 350.68 | 2.54 |
| 1 | 1 | 39 | E7 | 402.76 | 2.61 |
| 1 | 1 | 40 | E8 | 450.22 | 2.65 |
| 1 | 1 | 41 | E9 | 519.13 | 2.72 |
| 1 | 1 | 42 | EA | 596.60 | 2.78 |
| 1 | 1 | 43 | EB | 680.57 | 2.83 |
| 1 | 1 | 44 | EC | 782.43 | 2.89 |
| 1 | 1 | 45 | ED | 897.59 | 2.95 |
| 1 | 1 | 46 | EE | 1031.01 | 3.01 |
| 1 | 1 | 47 | EF | 1132.66 | 3.05 |
| 1 | 1 | 48 | F0 | 1323.89 | 3.12 |

| | | | | | |
|---|---|----|----|----------|------|
| 1 | 1 | 49 | F1 | 1526.38 | 3.18 |
| 1 | 1 | 50 | F2 | 1754.10 | 3.24 |
| 1 | 1 | 51 | F3 | 2000.94 | 3.30 |
| 1 | 1 | 52 | F4 | 2300.28 | 3.36 |
| 1 | 1 | 53 | F5 | 2638.52 | 3.42 |
| 1 | 1 | 54 | F6 | 3030.62 | 3.48 |
| 1 | 1 | 55 | F7 | 3476.12 | 3.54 |
| 1 | 1 | 56 | F8 | 3900.00 | 3.59 |
| 1 | 1 | 57 | F9 | 4495.88 | 3.65 |
| 1 | 1 | 58 | FA | 5165.49 | 3.71 |
| 1 | 1 | 59 | FB | 5890.72 | 3.77 |
| 1 | 1 | 60 | FC | 6771.07 | 3.83 |
| 1 | 1 | 61 | FD | 7764.20 | 3.89 |
| 1 | 1 | 62 | FE | 8916.89 | 3.95 |
| 1 | 1 | 63 | FF | 10224.04 | 4.08 |

Negative Polarity, Low Range

| Pos | Range | | Control | HV | Log |
|-----|--------|-------|---------|------|---------|
| Neg | Select | Level | HexByte | A-B | ABS(HV) |
| 1 | 0 | 0 | 80 | 0.13 | -0.89 |
| 1 | 0 | 1 | 81 | | |
| 1 | 0 | 2 | 82 | | |
| 1 | 0 | 3 | 83 | | |
| 1 | 0 | 4 | 84 | | |
| 1 | 0 | 5 | 85 | | |
| 1 | 0 | 6 | 86 | | |
| 1 | 0 | 7 | 87 | | |
| 1 | 0 | 8 | 88 | | |
| 1 | 0 | 9 | 89 | | |
| 1 | 0 | 10 | 8A | | |
| 1 | 0 | 11 | 8B | | |
| 1 | 0 | 12 | 8C | | |
| 1 | 0 | 16 | 8D | | |
| 1 | 0 | 14 | 8E | | |
| 1 | 0 | 15 | 8F | | |
| 1 | 0 | 16 | 90 | | |
| 1 | 0 | 17 | 91 | | |
| 1 | 0 | 18 | 92 | | |
| 1 | 0 | 19 | 93 | | |
| 1 | 0 | 20 | 94 | 0.18 | -0.74 |
| 1 | 0 | 21 | 95 | | |
| 1 | 0 | 22 | 96 | | |
| 1 | 0 | 23 | 97 | | |
| 1 | 0 | 24 | 98 | 0.23 | -0.64 |
| 1 | 0 | 25 | 99 | | |
| 1 | 0 | 26 | 9A | | |
| 1 | 0 | 27 | 9B | | |
| 1 | 0 | 28 | 9C | 0.31 | -0.51 |
| 1 | 0 | 29 | 9D | | |
| 1 | 0 | 30 | 9E | | |
| 1 | 0 | 31 | 9F | | |
| 1 | 0 | 32 | A0 | 0.42 | -0.38 |
| 1 | 0 | 33 | A1 | | |
| 1 | 0 | 34 | A2 | | |
| 1 | 0 | 35 | A3 | | |
| 1 | 0 | 36 | A4 | 0.65 | -0.19 |
| 1 | 0 | 37 | A5 | | |
| 1 | 0 | 38 | A6 | | |
| 1 | 0 | 39 | A7 | | |
| 1 | 0 | 40 | A8 | 1.01 | 0.004 |
| 1 | 0 | 41 | A9 | | |
| 1 | 0 | 42 | AA | 1.31 | 0.117 |
| 1 | 0 | 43 | AB | | |
| 1 | 0 | 44 | AC | 1.70 | 0.230 |
| 1 | 0 | 45 | AD | | |
| 1 | 0 | 46 | AE | 2.19 | 0.340 |
| 1 | 0 | 47 | AF | | |
| 1 | 0 | 48 | B0 | 2.76 | 0.441 |

| | | | | | |
|---|---|----|----|-------|-------|
| 1 | 0 | 49 | B1 | | |
| 1 | 0 | 50 | B2 | 3.63 | 0.560 |
| 1 | 0 | 51 | B3 | | |
| 1 | 0 | 52 | B4 | 4.73 | 0.675 |
| 1 | 0 | 53 | B5 | | |
| 1 | 0 | 54 | B6 | | |
| 1 | 0 | 55 | B7 | | |
| 1 | 0 | 56 | B8 | 7.43 | 0.871 |
| 1 | 0 | 57 | B9 | | |
| 1 | 0 | 58 | BA | 10.46 | 1.02 |
| 1 | 0 | 59 | BB | | |
| 1 | 0 | 60 | BC | 13.68 | 1.14 |
| 1 | 0 | 61 | BD | | |
| 1 | 0 | 62 | BE | 17.98 | 1.25 |
| 1 | 0 | 63 | BF | 20.62 | 1.31 |

DFLSV001.2. PPA Deflection Supply

The following provisional PPA deflection voltage levels were calculated from the formula $7.78 * \exp(0.135194 * (N - 21) / 2.0)$.

| N | Volts | eV | N | Volts | eV |
|----|--------|-------|----|----------|--------|
| 0 | -1.88 | 1.56 | 64 | -142.34 | 118.14 |
| 1 | -2.01 | 1.67 | 65 | -152.30 | 126.41 |
| 2 | -2.15 | 1.79 | 66 | -162.95 | 135.25 |
| 3 | -2.30 | 1.91 | 67 | -174.34 | 144.70 |
| 4 | -2.47 | 2.05 | 68 | -186.53 | 154.82 |
| 5 | -2.64 | 2.19 | 69 | -199.58 | 165.65 |
| 6 | -2.82 | 2.34 | 70 | -213.54 | 177.24 |
| 7 | -3.02 | 2.51 | 71 | -228.47 | 189.63 |
| 8 | -3.23 | 2.68 | 72 | -244.45 | 202.89 |
| 9 | -3.46 | 2.87 | 73 | -261.54 | 217.08 |
| 10 | -3.70 | 3.07 | 74 | -279.83 | 232.26 |
| 11 | -3.96 | 3.28 | 75 | -299.40 | 248.51 |
| 12 | -4.23 | 3.51 | 76 | -320.34 | 265.88 |
| 13 | -4.53 | 3.76 | 77 | -342.75 | 284.48 |
| 14 | -4.85 | 4.02 | 78 | -366.72 | 304.37 |
| 15 | -5.19 | 4.30 | 79 | -392.36 | 325.66 |
| 16 | -5.55 | 4.61 | 80 | -419.80 | 348.43 |
| 17 | -5.94 | 4.93 | 81 | -449.16 | 372.80 |
| 18 | -6.35 | 5.27 | 82 | -480.57 | 398.87 |
| 19 | -6.80 | 5.64 | 83 | -514.18 | 426.77 |
| 20 | -7.27 | 6.04 | 84 | -550.14 | 456.61 |
| 21 | -7.78 | 6.46 | 85 | -588.61 | 488.55 |
| 22 | -8.32 | 6.91 | 86 | -629.77 | 522.71 |
| 23 | -8.91 | 7.39 | 87 | -673.82 | 559.27 |
| 24 | -9.53 | 7.91 | 88 | -720.94 | 598.38 |
| 25 | -10.20 | 8.46 | 89 | -771.36 | 640.23 |
| 26 | -10.91 | 9.05 | 90 | -825.30 | 685.00 |
| 27 | -11.67 | 9.69 | 91 | -883.02 | 732.91 |
| 28 | -12.49 | 10.36 | 92 | -944.77 | 784.16 |
| 29 | -13.36 | 11.09 | 93 | -1010.84 | 839.00 |

| | | | | | |
|----|---------|--------|-----|-----------|---------|
| 30 | -14.30 | 11.87 | 94 | -1081.54 | 897.67 |
| 31 | -15.30 | 12.69 | 95 | -1157.17 | 960.45 |
| 32 | -16.36 | 13.58 | 96 | -1238.10 | 1027.62 |
| 33 | -17.51 | 14.53 | 97 | -1324.68 | 1099.49 |
| 34 | -18.73 | 15.55 | 98 | -1417.32 | 1176.38 |
| 35 | -20.04 | 16.64 | 99 | -1516.44 | 1258.65 |
| 36 | -21.45 | 17.80 | 100 | -1622.49 | 1346.67 |
| 37 | -22.95 | 19.04 | 101 | -1735.96 | 1440.85 |
| 38 | -24.55 | 20.38 | 102 | -1857.36 | 1541.61 |
| 39 | -26.27 | 21.80 | 103 | -1987.26 | 1649.42 |
| 40 | -28.10 | 23.33 | 104 | -2126.23 | 1764.77 |
| 41 | -30.07 | 24.96 | 105 | -2274.93 | 1888.19 |
| 42 | -32.17 | 26.70 | 106 | -2434.02 | 2020.24 |
| 43 | -34.42 | 28.57 | 107 | -2604.25 | 2161.52 |
| 44 | -36.83 | 30.57 | 108 | -2786.37 | 2312.69 |
| 45 | -39.40 | 32.71 | 109 | -2981.23 | 2474.42 |
| 46 | -42.16 | 34.99 | 110 | -3189.72 | 2647.47 |
| 47 | -45.11 | 37.44 | 111 | -3412.79 | 2832.62 |
| 48 | -48.26 | 40.06 | 112 | -3651.46 | 3030.71 |
| 49 | -51.64 | 42.86 | 113 | -3906.83 | 3242.66 |
| 50 | -55.25 | 45.86 | 114 | -4180.05 | 3469.44 |
| 51 | -59.11 | 49.06 | 115 | -4472.37 | 3712.07 |
| 52 | -63.25 | 52.50 | 116 | -4785.14 | 3971.67 |
| 53 | -67.67 | 56.17 | 117 | -5119.79 | 4249.42 |
| 54 | -72.40 | 60.10 | 118 | -5477.84 | 4546.60 |
| 55 | -77.47 | 64.30 | 119 | -5860.92 | 4864.57 |
| 56 | -82.88 | 68.79 | 120 | -6270.80 | 5204.76 |
| 57 | -88.68 | 73.61 | 121 | -6709.34 | 5568.75 |
| 58 | -94.88 | 78.75 | 122 | -7178.55 | 5958.20 |
| 59 | -101.52 | 84.26 | 123 | -7680.58 | 6374.88 |
| 60 | -108.62 | 90.15 | 124 | -8217.71 | 6820.70 |
| 61 | -116.21 | 96.46 | 125 | -8792.41 | 7297.70 |
| 62 | -124.34 | 103.20 | 126 | -9407.30 | 7808.06 |
| 63 | -133.04 | 110.42 | 127 | -10065.19 | 8354.11 |

BLR2PPA.0 Hydra Magnetometer Task BLR2PPA
September 29, 1996

BLR2PPA.1. Outline

1. Collect magnetometer data in ring buffer.
2. Get spin_phase time marker fixed wrt the BLR2PPA task.
3. Start BLR2PPA task and run filter on new magnetometer data.
4. Condition time variables and compute projection time.
5. Project Bx, By, and Bz to tT.
6. Convert Bx, By, and Bz to Theta, Phi.
7. Add zero to Phi to rotate to PPA reference frame, and condition Theta and Phi to range (null operation).
8. Compute new value of Kex using autoregressive filter and Bsq lookups.

BLR2PPA.2. Detail

BLR2PPA.2.1. Collect magnetometer data in ring buffer.

1. The magnetometer ISR collects the magnetometer data, which arrives one component at a time, with a complete reading every 9.2 ms. A complete reading is four components, [tS Bx By Bz]. The readings are stored in a ring buffer, or circular queue, that is 8 readings in circumference, so that it has a size of 8x4 2-byte words. This function is asynchronous to the PPA RAM refresh interval, called a PPR, which has a period of 18.0 ms.

2. The Bxyz interface is defined -- muddily -- by Figure 24 of the GIIS. This is a screwy figure. The way I interpret it, the bit-naming convention is contrary, the signal timing is not drawn to scale, and the jitter is drawn incorrectly, too. Namely, common usage and the rest of the Hydra instrument nomenclature follows the convention that the LSB of any item is Bit 0 and the MSB of a 16 bit word is bit 15; however Figure 24 of the GIIS clearly labels the bits the other way around, so that bit 15 is the LSB. Further, the SYNC/Scale, Bx, By, and Bz words should take only 16/55652=288 microseconds, which is about 10% of the interval between Enable Gates. Also, both of the 1 ms jitters are drawn outside the 9.2 ms interval, as if they delay the average time between samples, which I might then expect to be 9.2+0.5 ms. I believe the left arrow on the 9.2 ms bar should extend to the left-hand timing mark labelled "1 mS jitter."

3. As shown in Figure 24 of the GIIS, the first component of each reading is a 2 byte timing and ranging word. Using the GIIS convention, the 12 LSB's (let's call them GIIS-bits 4-15) are the 12-bit spin phase count at the time of the

Bxyz sample. This number counts upward after being reset by the Spin Clock once per spacecraft revolution. GIIS-bit 3 is labeled Cal/Flipper Mode, or Snapshot Mode, and doesn't matter to us. GIIS-bits 0-2 designate which magnetometer the reading is from, and the gain, as shown below.

| GIIS-bits 0-3 (as a hex nibble) | 8 or 9 | a or b | 4 or 5 | 6 or 7 |
|---------------------------------|---------|---------|----------|----------|
| Range Word GIIS-bit 0 | 1 | 1 | 0 | 0 |
| Range Word GIIS-bit 1 | 0 | 0 | 1 | 1 |
| Range Word GIIS-bit 2 | 0 | 1 | 0 | 1 |
| Magnetometer Selection | inboard | inboard | outboard | outboard |
| Gain or Sensitivity | low | high | low | high |
| Unipolar Range, nT | 45,000 | 5,625 | 5,400 | 675 |
| Expected Measurement Noise, nT | 4.1 | 2.6 | 0.16 | 0.14 |

Extract GIIS-bits 0-3 and insert them in a four-bit status field PPBSTAT. Overwrite this field each time BLR2PPA is called. The most recent value will be picked up four times a major frame by the science housekeeping telemetry.

4. The magnetic field readings Bx, By and Bz are 16-bit signed integers using the two's complement sign convention, and the full scale reading corresponds to the unipolar range shown above. In each case the total magnetometer range is + and - the unipolar range. For the outboard magnetometer, the measurement noise is expected to be sensor noise, and for the inboard magnetometer, the measurement noise is expected to be system noise.

BLR2PPA.2.2. Get spin_phase time marker fixed wrt the BLR2PPA task.

The BCI before the BLR2PPA task reads tR1 from ET1 register and inserts the value in variable location "spin_phase". ET1 is reset by the delayed sun pulse, and clocked by the spin clock.

This feature is not implemented as of April, 1993. Instead, we use an average projection time as described in section BLR2PPA.2.4. steps 6 and 13.

BLR2PPA.2.3. Start BLR2PPA task and run filter on new magnetometer data.

The BLR2PPA task is enabled by the PPSCAN task and run right after it. It must be completed at the end of the PPR, or PPA RAM refresh interval, in time for the ET2 interrupt that stops the PPA and initializes the PPA service task.

Each time the BLR2PPA task is entered, it must first identify all new magnetometer readings that have arrived since the last BLR2PPA task, and run them through a filter algorithm.

The filter code is contained in a subroutine called from the BLR2PPA task. Since the BLR2PPA task and the magnetometer ISR are asynchronous, the number of new readings may vary. It is important to keep the readings in sets and not to mix components of different readings.

The filter is first-order, or linear, in a despun reference frame. An autoregressive (AR) algorithm is used for the three components Bx, By, and Bz. Bx and By are coupled in order to despun the reference frame; Bz is independent.

BLR2PPA.2.3.1. The Despun Linear Filter Algorithm

The quantities that are needed by the BLR2PPA task are the components of the six-vector [Bxplus Bxdotplus Byplus Bydotplus Bzplus Bzdotplus]' and time tS. Quantities are carried in double precision (4 byte integers) up to the point where projected values are computed. The conversion to Theta and Phi is done in single precision.

(0) Initialize the predicted values,

```
Bzminus = 0  
Bzdotminus = 0  
Bxminus = 0  
Bxdotminus = 0  
Byminus = 0  
Bydotminus = 0  
BsqBar = 0
```

All RAM locations are zeroed at power up. This is all the initialization needed, as the filter converges from any initial position.

(1) Calculate Residues.

For each new reading, [Bxmeas Bymeas Bzmeas]', form the residues,

```
Rx = Bxmeas - BxOffs - Bxminus  
Ry = Bymeas - ByOffs - Byminus  
Rz = Bzmeas - BzOffs - Bzminus.
```

The quantities BxOffs, ByOffs, and BzOffs represent empirical offsets which may need to be applied after launch. They should reside in the program as variables, whose nominal values are 0 so as to produce a null operation upon being added to Bxmeas, etc, but which can be changed by poking values into their storage locations. As there must be a different set of offsets for each magnetometer sensor and range, there are actually 12 values which reside in a table indexed by the magnetometer range identification.

(2) Compute the corrected values.

```
Bxplus = Bxminus + K1*Rx
```

```

Bxdotplus = Bxdotminus + K2*Rx
Byplus = Byminus + K1*Ry
Bydotplus = Bydotminus + K2*Ry
Bzplus = Bzminus + K1*Rz
Bzdotplus = Bzdotminus + K2*Rz

```

The values of K1 and K2 are of the form $1/2^N$, so that the multiplications can be performed by N right shifts of the quantities Rx, Ry, and Rz. K1 and K2, called the filter gains, are discussed below.

(3) Associate result with tS.

Associate the time tS of the last measurement with the six-vector, [Bxplus Bxdotplus Byplus Bydotplus Bzplus Bzdotplus]' for the projection computation performed later in the BLR2PPA task. This set of 7 readings must be used together.

(4) Compute the next predicted values.

$$\begin{vmatrix} \text{Bxminus} \\ \text{Bxdotminus} \\ \text{Byminus} \\ \text{Bydotminus} \\ \text{Bzminus} \\ \text{Bzdotminus} \end{vmatrix} = \begin{vmatrix} 1 & 1 & S & S & 0 & 0 \\ 0 & 1 & 0 & S & 0 & 0 \\ -S & -S & 1 & 1 & 0 & 0 \\ 0 & -S & 0 & 1 & 0 & 0 \\ 0 & 0 & 0 & 0 & 1 & 1 \\ 0 & 0 & 0 & 0 & 0 & 1 \end{vmatrix} \begin{vmatrix} \text{Bxplus} \\ \text{Bxdotplus} \\ \text{Byplus} \\ \text{Bydotplus} \\ \text{Bzplus} \\ \text{Bzdotplus} \end{vmatrix}$$

This computation can be organized as follows.

$$\begin{aligned}
\text{Bxboth} &= \text{Bxplus} + \text{Bxdotplus} \\
\text{Byboth} &= \text{Byplus} + \text{Bydotplus} \\
\text{Bxminus} &= \text{Bxboth} + S*\text{Byboth} \\
\text{Bxdotminus} &= \text{Bxdotplus} + S*\text{Bydotplus} \\
\text{Byminus} &= \text{Byboth} - S*\text{Bxboth} \\
\text{Bydotminus} &= \text{Bydotplus} - S*\text{Bxdotplus} \\
\text{Bzminus} &= \text{Bzplus} + \text{Bzdotplus} \\
\text{Bzdotminus} &= \text{Bzdotplus}
\end{aligned}$$

The rotational sine factor, $S = 0.00963$, and is well approximated by

$$S = 1/2^7 + 1/2^9 = 0.00977 = \sin(2\pi \cdot 0.0092 / 5.9192)$$

Thus these multiplications can be accomplished by two shift operations and an add operation. It may be advantageous to do the $1/2^7$ shift, duplicate the $1/2^7$ result, do a $1/2^2$ shift on the $1/2^7$ result to form the $1/2^9$ result, and add the $1/2^7$ result to the $1/2^9$ result.

(5) End loop.

If there is another new reading, go to (1) and run it through the filter. If there is no new reading, proceed to the projection section of the task.

The computational burden of the prediction-correction filter is approximately 14 shift operations, 20 add operations, and 26 move operations.

BLR2PPA.2.3.2. The Filter Gains

The filter gains, K1 and K2, are taken from a table which is addressed by an index, Kex. The default values can be computed from Kex by the following formulas:

$$K1 = 1/2^Kex$$
$$K2 = 1/2^{(2*Kex+1)}$$

Other values of K1 and K2 may be uploaded from the ground. The index Kex is computed adaptively in flight as described in BLR2PPA.2.8. The range of useful values is 0 to 7. The lower values of Kex give a more aggressive filter that does a better job of following a varying signal, but is susceptible to measurement noise. The higher values of Kex are useful when the measurement noise is higher, but they cannot follow such a rapidly varying signal. Note that, since the filter despins the reference frame, we are talking about signal variations in a despun reference frame.

BLR2PPA.2.4. Condition time variables and compute projection time.

The projection to the target time, tT, in the middle of the PPR, involves several contributions.

1. First there is the phase lag of the magnetometer filters. Before the reading receives its timing mark there is a phase lag of 7 ms for UCLA's digital filter plus about 2 ms for the analog circuitry. Thus the reading is already 9 ms old at the time it is labeled with the spin phase count of the Bxyz sample. At the nominal spin period of 6 s, this is 6.1 SPT's.

2. Plus the time required to feed the four components to our instrument. The reading is available to the Bxyz interface at the instant it is tagged with the spin phase count. There is a jitter of 0 to 1 ms before the first word gate of the sample, 2 ms between word gates, and 0.3 ms for each word gate. That's an average delay of $0.5 + 3*2 + 0.3 = 6.8 \pm 0.5$ ms before our instrument has all of it.

3. Because the magnetometer readings occur at discrete intervals, every 9.2 ms, there is on the average a wait before the BLR2PPA task picks up the most recent value. This is 4.6 ± 4.6 ms.

4. Add the constant value of tT-tR, which is the time between the BCI interrupt which initiates the BLR2PPA task, and the target time of the PPA reading. In ModeZero $tT-tR = 1.4*1000$ ticks of the telemetry clock (1400 TMT's) which translates to $1400/55652 = 0.0252$ s, or about 17.2 ticks of the spin clock (17.2 SPT's).

5. Subtract the time between tR, the BCI interrupt which initiates the BLR2PPA task, and the moment when the task picks up the most recent value. This time is about 3 ms, and is subject to refinement as we test and change the code.

6. All of the above adds up to $(9 + 6.8 + 4.6 + 25.2 - 3) \pm 0.5$ ms. This is to say
42.6 ± 5.1 ms,
29.1 ± 3.5 SPT's,
4.63 ± 0.55 BSP's.

If we are willing to live with this much uncertainty, we can project by the average time given here. A way to eliminate this uncertainty is given in steps 7-12 below.

7. We can eliminate the major uncertainty if we make use of the time tag that comes with the magnetometer reading. The key to doing this is the spin_phase time marker named in BLR2PPA.2.2. This gives us the spin phase clock reading 17.2 SPT's before the reading is to be used. Then, each time the BLR2PPA routine is called, we can obtain the particular value of the variable delay tR-tS, between tS, the time label of the last magnetometer sample, and tR, the time of the BCI interrupt which initiates the BLR2PPA task. There is jitter over an envelope of 9.2 ms or 6.3 SPT's in this quantity, since the magnetometer sample time is not synchronized with the BCI. Sometimes tS may even be later than tR, depending upon the time between the BCI and the execution of the BLR2PPA task. It must be conditioned as follows.

8. Obtain the value of tR1 from location "spin_phase" and complement it (because ET1 is a down-counter). The result, called tR1bar, should follow the pattern: if tR1=ffff, tR1bar=0000; if tR1=fffe, tR1bar=0001; etc. (For tR1, see BLR2PPA.2.2.)

9. Add sun pulse delay tD to tR1bar. Put tR == tD+tR1bar on an ascending scale corresponding to 0 immediately after the sun pulse. Note that the total value for tR may be >4095, which only means that tR is referred to a prior sun pulse, and the most recent sun pulse is still propagating through the sun pulse delay counter.

10. Obtain tS from the most recent magnetometer reading (See BLR2PPA.2.3.1., step (3)). The spin phase counter we get from the magnetometer is contained in the 12 LSB's of the magnetometer synch/scale word, on an ascending scale from 0 to 4095, beginning with 0 immediately after the sun pulse.

11. Form the difference tR-tS. Subtract 4096 if tR-tS > 4096. Add 4096 if tR-tS < -512. Note that tR-tS may be slightly negative if the magnetometer interrupt occurs between the BCI and BLR2PPA; that's fine. However, tR-tS may also be very negative if the sun pulse and delayed sun pulse occur before the first magnetometer interrupt following the sun pulse; this is the case for which we add 4096.

12. The projection interval tJSPT is thus:

$$\begin{aligned} tJSPT &= 6.1 && \text{age before time tag is applied} \\ &+ 17.2 && tT-tR \\ &+ tR-ts && \text{variable calculated in step 11} \\ &= 23.3 + (tR-ts) \quad \text{SPT's} \end{aligned}$$

The unit of time used by the filter is the magnetometer sample period, BSP = 9.2 ms. At the nominal spin period of 6 s, there are 6.28 SPT/BSP. Thus

$$tJBSP = 3.7 + (tR-ts)/6.28 \quad \text{BSP's}$$

In section BLR2PPA.2.5. below, we approximate tJBSP by

$$tJ = 4 + (5*(tR-ts)-9)/32$$

where tR-ts is in SPT units and tJ is in BSP units.

13. In the absence of a spin phase time marker, we can use 6 for the value of tR-ts. This gives the average projection time given above in step 6. Note that this value errs by as much as 0.55 BSP's.

BLR2PPA.2.5. Project Bx, By, and Bz to tT.

Compute the projected values.

$$\begin{vmatrix} Bxproj \\ Byproj \\ Bzproj \end{vmatrix} = \begin{vmatrix} 1 & tJ & SJ & tJ*SJ & 0 & 0 \\ -SJ & -tJ*SJ & 1 & tJ & 0 & 0 \\ 0 & 0 & 0 & 0 & 1 & tJ \end{vmatrix} \begin{vmatrix} Bxplus \\ Bxdotplus \\ Byplus \\ Bydotplus \\ Bzplus \\ Bzdotplus \end{vmatrix}$$

$SJ = tJ*S$, where S is given in BLR2PPA.2.1.1.

Although this is a straightforward calculation, we can probably make it faster on our fixed point cpu by being devious. In BSP units, write

$$\begin{aligned} tJ &= 4 + tJ' \\ \text{and } tJ^2 &= 16 + 8*tJ' \quad (+ \text{error term} = (tJ')^2) \end{aligned}$$

where $tJ' = (5*(tR-ts)-9)/32$, and tR-ts is in SPT units as it was calculated above. We don't compute tJ' yet. Now,

$$\begin{aligned} \begin{vmatrix} Bxproj \\ Byproj \\ Bzproj \end{vmatrix} &= \begin{vmatrix} 1 & 4S & 0 \\ -4S & 1 & 0 \\ 0 & 0 & 1 \end{vmatrix} \begin{vmatrix} Bxplus + 4*Bxdotplus \\ Byplus + 4*Bydotplus \\ Bzplus + 4*Bzdotplus \end{vmatrix} \\ &+ tJ' * \begin{vmatrix} 0 & 1 & S & 8S & 0 & 0 \\ -S & -8S & 0 & 1 & 0 & 0 \end{vmatrix} \begin{vmatrix} Bxplus \\ Bxdotplus \end{vmatrix} \end{aligned}$$

| | | | | | | | | |
|--|---|---|---|---|---|---|--|------------------|
| | 0 | 0 | 0 | 0 | 0 | 1 | | |
| | | | | | | | | Byplus |
| | | | | | | | | Bydotplus |
| | | | | | | | | Bzplus |

Bzdotplus

with $S = 1/2^7 + 1/2^9$
 $4S = 1/2^5 + 1/2^7$

The calculation can be organized in a sequence similar to that in BLR2PPA.2.1.1., section (4). Form

```

Bx4 = Bxplus+4*Bxdotplus      (1 shift and 1 add)
By4 = Byplus+4*Bydotplus      (1 shift and 1 add)
Bz4 = Bzplus+4*Bzdotplus      (1 shift and 1 add)
Bx8 = Bxplus+8*Bxdotplus      (1 shift and 1 add)
By8 = Byplus+8*Bydotplus      (1 shift and 1 add)
tJ'num = (5*(tR-tS)-9)        (1 mul and 1 add)
BxJ' = (Bxdotplus+S*By8)*tJ'num/32 (1 mul, 2 adds, and 3 shifts)
ByJ' = (Bydotplus-S*Bx8)*tJ'num/32 (1 mul, 2 adds, and 3 shifts)
Bxproj = Bx4 + 4S*By4 + BxJ'    (3 adds and 1 shift)
Byproj = By4 - 4S*Bx4 + ByJ'    (3 adds and 1 shift)
Bzproj = Bz4 + Bzdotplus*tJ'num/32 (1 mul, 1 add, and 1 shift)

```

Total cost is approximately 4 mul, 17 adds, 14 shifts, and TBD moves, plus all the fooling around with time lines, and lack of transparency in the coding.

BLR2PPA.2.6. Convert Bx, By, and Bz to Theta, Phi.

In the following, read Bxproj for Bx, etc. Quantities are given as 16 bit integers.

1. Theta and Phi are defined by

```

Theta = arctan(Bz/(sqrt(Bx**2+By**2)))
Phi = arctan(By/Bx)

```

They are computed from

```

Theta = arcsqtan(Bz**2/(Bx**2+By**2))
Phi = arcsqtan(By**2/Bx**2)

```

where $\text{arcsqtan}(X**2) == \arctan(X)$

2. Compute Bx^{**2} , By^{**2} , Bz^{**2} , and $Bx^{**2}+By^{**2}$.

3. For Theta:

(a) Determine the octant of Theta. Octants 5-8 are unavailable for Theta.

- (i) If $Bz > 0$, octants 1 or 2
If $Bz < 0$, octants 3 or 4
- (ii) If $Bz^{**2} < (Bx^{**2}+By^{**2})$, octants 2 or 3
If $Bz^{**2} > (Bx^{**2}+By^{**2})$, octants 1 or 4

(b) Compute the indexing integer INDINT, $(0 \leq \text{INDINT} \leq \text{MULT})$:

```

INDINT = INT(MULT*Bz**2/(Bx**2+By**2)) for octants 2 & 3
INDINT = INT(MULT*(Bx**2+By**2)/Bz**2) for octants 1 & 4

```

where MULT is an integer which may have the value 31528 decimal (31528 worked on my spreadsheet.) MULT was chosen to use the

range of a 16 bit integer with best resolution between the angle quanta chosen by VanDiver for the PPA board inputs.

(c) Using the index INDINT, search for the index angle in a table of length 32. The values of the index angle progress from 0 to 31 as shown in Appendix APXB2PPA. This is a search, not a straight indexed lookup. It may be a binary or linear search, depending upon the speed in the pipeline of the processor.

(d) Derive Theta from the index angle:

For octant 1, Theta = index angle
For octant 2, Theta = 63 - index angle
For octant 3, Theta = 127 - index angle
For octant 4, Theta = 64 + index angle

Appendix APXB2PPA shows the desired results in decimal notation.

4. For Phi:

- (a) Determine the octant of Phi from By and Bx.
(b) Compute the indexing integer, INDINT:

INDINT = INT(MULT*(By**2/Bx**2)), octants 1, 4, 5, and 8
INDINT = INT(MULT*(Bx**2/By**2)), octants 2, 3, 6, and 7

where MULT is the same as used to obtain Theta.

(c) Using the index INDINT, look up the index angle in the same table used for Theta.

(d) Derive Phi from the index angle:

For octant 1, Phi = index angle
For octant 2, Phi = 63 - index angle
For octant 3, Phi = 64 + index angle
For octant 4, Phi = 127 - index angle
For octant 5, Phi = 128 + index angle
For octant 6, Phi = 191 - index angle
For octant 7, Phi = 192 + index angle
For octant 8, Phi = 255 - index angle

Appendix APXB2PPA shows the desired results in decimal notation.

BLR2PPA.2.7. Add zero degrees to Phi to rotate to PPA reference frame, and condition to range. This became a null operation when the PAS incorporated this rotation.

0. This information is left in the document in case I ever need to review it.

1. VanDiver defined the PPA x-axis to go through the "B" codacon, with Phi increasing counterclockwise around the xy plane from the x-axis.

2. In spacecraft coordinates, the Xsc-axis goes through the magnetometer boom, and the spin axis is the positive Zsc-axis, so that the Xsc-Ysc plane is the spin equator.

3. We get our magnetometer data in spacecraft coordinates.

4. At the CDR in March, 1990, a figure showed "PPA#2" to be at an angle of 70 +- 1 degrees measured counterclockwise from the spacecraft x-axis in the spacecraft x-y plane.

However, GSFC Drawing 1308201 dated 9/22/90 shows PPA#2 to be at an angle of 249 degrees measured in the spacecraft x-y

plane counterclockwise about the spacecraft z-axis. This drawing was based on GE drawings number 23002009 and 23001010 which were received by GSFC 9/11/90.

This represents a switch between #1 and #2 and a shift of 1 degree, which was within the original tolerances. We will suppose the latter information supercedes the former.

5. The pin assignments for the codacon connectors confirm that the B codacon is in PPA#2. Then add 111 degrees to Phi to put it in the PPA reference frame. That is, add 79 (78.9) to the digital representation for Phi computed in BLR2PPA_0.2.6.

6. In October, 1991, John Keller issued a memo defining coordinates, and Jim VanDiver incorporated this rotation in the PAS board. Therefore, we feed the PAS board magnetometer theta and phi values in spacecraft coordinates, and no further rotation is needed to change between spacecraft and detector coordinates. The PAS board knows how the codacons are oriented. I am leaving this section in my FID just in case I ever need to review the basis of our coordinates.

7. At this point, the ranges for Theta and Phi should be 0-127 and 0-255, respectively. Neither should need conditioning at this point, because they were created in range and never changed. Further, Phi is a one byte word, and would overflow gracefully, anyway.

BLR2PPA.2.8. Compute new value of Kex using autoregressive filter and Bsq lookup table.

1. Compute $Bsq = Bx^2 + By^2 + Bz^2$, from elements which were computed in BLR2PPA.2.6. step 2.

2. Compute $BsqBar = BsqBar * (1 - 2^{-5}) + Bsq * 2^{-5}$.

3. Using current value of Kex, magnetometer select, and magnetometer sensitivity (See BLR2PPA.2.1.0.), look up max and min limits from Bsq lookup table. If BsqBar exceeds max, decrement Kex by 1. If min exceeds BsqBar, increment Kex by 1. If min < BsqBar < max, leave Kex as is. Note limits to Kex are 0 and 7 (the table should cover these limits), and note that Kex changes by no more than 1 each time.

4. The updated value of Kex will be used the next time BLR2PPA is called.

5. Tables of Critical Values for B and B^2 for Selected Value of Kex

| K e Crit x N/S | (inboard, low), (8 or 9) Range=45000 nT, N=4.1 nT Crit Sig Crit S^2 (nT) int integer (lo, hi) | (inboard, high), (a or b) Range=5625 nT, N=2.6 nT Crit Sig Crit S^2 (nT) int integer (lo, hi) |
|----------------------|--|--|
| 7 | 0 0 1584 0 0 40780 | |
| 6 .11 | 37 27 736 5052 24 138 18957 130039 | |
| 5 .075 | 55 40 1584 11368 35 202 40780 292589 | |
| 4 .042 | 98 71 5052 26907 62 361 130039 692519 | |
| 3 .028 | 146 107 11368 110035 93 541 292589 2831978 | |

| | | | | | | | | | |
|---|--------|------|-----|--------|------------|-----|------|----------|------------|
| 2 | .0182 | 225 | 164 | 26907 | 843819 | 143 | 832 | 692519 | 21717422 |
| 1 | .009 | 456 | 332 | 110035 | 13498276 | 289 | 1683 | 2831978 | 347449600 |
| 0 | .00325 | 1262 | 919 | 843819 | 1073676289 | 800 | 4660 | 21717422 | 1073676289 |

| K | (outboard, low), (4 or 5) | | | | (outboard, high), (6 or 7) | | | | |
|--------|---------------------------|-----|---------|----------|----------------------------|-----|---------|----------|------------|
| e Crit | Range=5400 nT, N=0.16 nT | | | | Range=675 nT, N=0.14 nT | | | | |
| x N/S | Crit | Sig | Crit | S^2 | Crit | Sig | Crit | S^2 | |
| | (nT) | int | integer | (lo, hi) | (nT) | int | integer | (lo, hi) | |
| 7 | | 0 | 0 | 167 | | 0 | 0 | 8211 | |
| 6 | .11 | 1 | 9 | 77 | 534 | 1 | 62 | 3817 | 26183 |
| 5 | .075 | 2 | 13 | 167 | 1202 | 2 | 91 | 8211 | 58912 |
| 4 | .042 | 4 | 23 | 534 | 2845 | 3 | 162 | 26183 | 139437 |
| 3 | .028 | 6 | 35 | 1202 | 11636 | 5 | 243 | 58912 | 570212 |
| 2 | .0182 | 9 | 53 | 2845 | 89239 | 8 | 373 | 139437 | 4372755 |
| 1 | .009 | 18 | 108 | 11636 | 1425636 | 16 | 755 | 570212 | 69956496 |
| 0 | .00325 | 49 | 299 | 89239 | 1073676289 | 43 | 2091 | 4372755 | 1073676289 |

APPENDIX APXB2PPA: See File APXB2PPA.FID.

File APXB2PPA.FID

APPENDIX APXB2PPA
September 29, 1996

From B2PPA.CAL

1.41deg = 2*pi/256 rad = Q, the Angular Quantum

| Angle (degrees) > Index | | | | Index > Angle (VanDiver quanta) | | | | Decimal Representation of Vandiver Scale | |
|-------------------------|-------|---------|----------|---------------------------------|-------|----------|----------|--|-----|
| Mltiplier= | 31528 | Mltpllr | Mltplrlr | * | * | | | Tht | Phi |
| Min | Max | TrgSqMn | TrgSqMx | | | | | | |
| 0 | 1.41 | 0 | 18.9999 | 0 | 18 | 0 | 1.000003 | 0 | 0 |
| 1.41 | 2.81 | 18.9999 | 76.0912 | 19 | 75 | 1.000003 | 1.998803 | 1 | 1 |
| 2.81 | 4.22 | 76.0912 | 171.550 | 76 | 171 | 1.998803 | 3.003919 | 2 | 2 |
| 4.22 | 5.63 | 171.550 | 305.839 | 172 | 305 | 3.003919 | 4.001045 | 3 | 3 |
| 5.63 | 7.03 | 305.839 | 479.614 | 306 | 479 | 4.001045 | 5.001991 | 4 | 4 |
| 7.03 | 8.44 | 479.614 | 693.728 | 480 | 693 | 5.001991 | 6.001157 | 5 | 5 |
| 8.44 | 9.84 | 693.728 | 949.244 | 694 | 948 | 6.001157 | 6.999119 | 6 | 6 |
| 9.84 | 11.3 | 949.244 | 1247.44 | 949 | 1246 | 6.999119 | 7.998622 | 7 | 7 |
| 11.3 | 12.7 | 1247.44 | 1589.83 | 1247 | 1589 | 7.998622 | 9.000457 | 8 | 8 |
| 12.7 | 14.1 | 1589.83 | 1978.18 | 1590 | 1977 | 9.000457 | 9.999554 | 9 | 9 |
| 14.1 | 15.5 | 1978.18 | 2414.53 | 1978 | 2414 | 9.999554 | 11.00103 | 10 | 10 |
| 15.5 | 16.9 | 2414.53 | 2901.18 | 2415 | 2900 | 11.00103 | 11.99965 | 11 | 11 |
| 16.9 | 18.3 | 2901.18 | 3440.80 | 2901 | 3440 | 11.99965 | 13.00036 | 12 | 12 |
| 18.3 | 19.7 | 3440.80 | 4036.37 | 3441 | 4035 | 13.00036 | 13.99941 | 13 | 13 |
| 19.7 | 21.1 | 4036.37 | 4691.28 | 4036 | 4690 | 13.99941 | 14.99959 | 14 | 14 |
| 21.1 | 22.5 | 4691.28 | 5409.35 | 4691 | 5408 | 14.99959 | 15.99953 | 15 | 15 |
| 22.5 | 23.9 | 5409.35 | 6194.87 | 5409 | 6194 | 15.99953 | 17.00016 | 16 | 16 |
| 23.9 | 25.3 | 6194.87 | 7052.68 | 6195 | 7052 | 17.00016 | 18.00036 | 17 | 17 |
| 25.3 | 26.7 | 7052.68 | 7988.22 | 7053 | 7987 | 18.00036 | 18.99978 | 18 | 18 |
| 26.7 | 28.1 | 7988.22 | 9007.62 | 7988 | 9007 | 18.99978 | 20.00036 | 19 | 19 |
| 28.1 | 29.5 | 9007.62 | 10117.8 | 9008 | 10117 | 20.00036 | 21.00018 | 20 | 20 |
| 29.5 | 30.9 | 10117.8 | 11326.5 | 10118 | 11326 | 21.00018 | 22.00038 | 21 | 21 |
| 30.9 | 32.3 | 11326.5 | 12642.6 | 11327 | 12642 | 22.00038 | 23.00027 | 22 | 22 |
| 32.3 | 33.8 | 12642.6 | 14076.1 | 12643 | 14075 | 23.00027 | 23.99995 | 23 | 23 |
| 33.8 | 35.2 | 14076.1 | 15638.2 | 14076 | 15637 | 23.99995 | 24.99988 | 24 | 24 |
| 35.2 | 36.6 | 15638.2 | 17341.8 | 15638 | 17341 | 24.99988 | 26.00009 | 25 | 25 |
| 36.6 | 38.0 | 17341.8 | 19201.7 | 17342 | 19201 | 26.00009 | 27.00016 | 26 | 26 |
| 38.0 | 39.4 | 19201.7 | 21234.5 | 19202 | 21234 | 27.00016 | 28.00022 | 27 | 27 |
| 39.4 | 40.8 | 21234.5 | 23459.6 | 21235 | 23459 | 28.00022 | 29.00016 | 28 | 28 |
| 40.8 | 42.2 | 23459.6 | 25899.2 | 23460 | 25898 | 29.00016 | 29.99994 | 29 | 29 |
| 42.2 | 43.6 | 25899.2 | 28578.7 | 25899 | 28578 | 29.99994 | 31.00011 | 30 | 30 |
| 43.6 | 45 | 28578.7 | 31528 | 28579 | 31527 | 31.00011 | 32 | 31 | 31 |
| 45 | 46.4 | 31528 | 28578.7 | 31528 | 28578 | 32 | 31.00011 | 32 | 32 |
| 46.4 | 47.8 | 28578.7 | 25899.2 | 28579 | 25898 | 31.00011 | 29.99994 | 33 | 33 |
| 47.8 | 49.2 | 25899.2 | 23459.6 | 25899 | 23459 | 29.99994 | 29.00016 | 34 | 34 |
| 49.2 | 50.6 | 23459.6 | 21234.5 | 23460 | 21234 | 29.00016 | 28.00022 | 35 | 35 |
| 50.6 | 52.0 | 21234.5 | 19201.7 | 21235 | 19201 | 28.00022 | 27.00016 | 36 | 36 |
| 52.0 | 53.4 | 19201.7 | 17341.8 | 19202 | 17341 | 27.00016 | 26.00009 | 37 | 37 |
| 53.4 | 54.8 | 17341.8 | 15638.2 | 17342 | 15637 | 26.00009 | 24.99988 | 38 | 38 |
| 54.8 | 56.3 | 15638.2 | 14076.1 | 15638 | 14075 | 24.99988 | 23.99995 | 39 | 39 |

| | | | | | | | | | |
|------|------|---------|---------|-------|-------|----------|----------|-----|----|
| 56.3 | 57.7 | 14076.1 | 12642.6 | 14076 | 12642 | 23.99995 | 23.00027 | 40 | 40 |
| 57.7 | 59.1 | 12642.6 | 11326.5 | 12643 | 11326 | 23.00027 | 22.00038 | 41 | 41 |
| 59.1 | 60.5 | 11326.5 | 10117.8 | 11327 | 10117 | 22.00038 | 21.00018 | 42 | 42 |
| 60.5 | 61.9 | 10117.8 | 9007.62 | 10118 | 9007 | 21.00018 | 20.00036 | 43 | 43 |
| 61.9 | 63.3 | 9007.62 | 7988.22 | 9008 | 7987 | 20.00036 | 18.99978 | 44 | 44 |
| 63.3 | 64.7 | 7988.22 | 7052.68 | 7988 | 7052 | 18.99978 | 18.00036 | 45 | 45 |
| 64.7 | 66.1 | 7052.68 | 6194.87 | 7053 | 6194 | 18.00036 | 17.00016 | 46 | 46 |
| 66.1 | 67.5 | 6194.87 | 5409.35 | 6195 | 5408 | 17.00016 | 15.99953 | 47 | 47 |
| 67.5 | 68.9 | 5409.35 | 4691.28 | 5409 | 4690 | 15.99953 | 14.99959 | 48 | 48 |
| 68.9 | 70.3 | 4691.28 | 4036.37 | 4691 | 4035 | 14.99959 | 13.99941 | 49 | 49 |
| 70.3 | 71.7 | 4036.37 | 3440.80 | 4036 | 3440 | 13.99941 | 13.00036 | 50 | 50 |
| 71.7 | 73.1 | 3440.80 | 2901.18 | 3441 | 2900 | 13.00036 | 11.99965 | 51 | 51 |
| 73.1 | 74.5 | 2901.18 | 2414.53 | 2901 | 2414 | 11.99965 | 11.00103 | 52 | 52 |
| 74.5 | 75.9 | 2414.53 | 1978.18 | 2415 | 1977 | 11.00103 | 9.999554 | 53 | 53 |
| 75.9 | 77.3 | 1978.18 | 1589.83 | 1978 | 1589 | 9.999554 | 9.000457 | 54 | 54 |
| 77.3 | 78.8 | 1589.83 | 1247.44 | 1590 | 1246 | 9.000457 | 7.998622 | 55 | 55 |
| 78.8 | 80.2 | 1247.44 | 949.244 | 1247 | 948 | 7.998622 | 6.999119 | 56 | 56 |
| 80.2 | 81.6 | 949.244 | 693.728 | 949 | 693 | 6.999119 | 6.001157 | 57 | 57 |
| 81.6 | 83.0 | 693.728 | 479.614 | 694 | 479 | 6.001157 | 5.001991 | 58 | 58 |
| 83.0 | 84.4 | 479.614 | 305.839 | 480 | 305 | 5.001991 | 4.001045 | 59 | 59 |
| 84.4 | 85.8 | 305.839 | 171.550 | 306 | 171 | 4.001045 | 3.003919 | 60 | 60 |
| 85.8 | 87.2 | 171.550 | 76.0912 | 172 | 75 | 3.003919 | 1.998803 | 61 | 61 |
| 87.2 | 88.6 | 76.0912 | 18.9999 | 76 | 18 | 1.998803 | 1.000003 | 62 | 62 |
| 88.6 | 90 | 18.9999 | 0 | 19 | 0 | 1.000003 | 0 | 63 | 63 |
| 90 | 91.4 | 0 | 18.9999 | 0 | 18 | 0 | 1.000003 | 127 | 64 |
| 91.4 | 92.8 | 18.9999 | 76.0912 | 19 | 75 | 1.000003 | 1.998803 | 126 | 65 |
| 92.8 | 94.2 | 76.0912 | 171.550 | 76 | 171 | 1.998803 | 3.003919 | 125 | 66 |
| 94.2 | 95.6 | 171.550 | 305.839 | 172 | 305 | 3.003919 | 4.001045 | 124 | 67 |
| 95.6 | 97.0 | 305.839 | 479.614 | 306 | 479 | 4.001045 | 5.001991 | 123 | 68 |
| 97.0 | 98.4 | 479.614 | 693.728 | 480 | 693 | 5.001991 | 6.001157 | 122 | 69 |
| 98.4 | 99.8 | 693.728 | 949.244 | 694 | 948 | 6.001157 | 6.999119 | 121 | 70 |
| 99.8 | 101. | 949.244 | 1247.44 | 949 | 1246 | 6.999119 | 7.998622 | 120 | 71 |
| 101. | 103. | 1247.44 | 1589.83 | 1247 | 1589 | 7.998622 | 9.000457 | 119 | 72 |
| 103. | 104. | 1589.83 | 1978.18 | 1590 | 1977 | 9.000457 | 9.999554 | 118 | 73 |
| 104. | 105. | 1978.18 | 2414.53 | 1978 | 2414 | 9.999554 | 11.00103 | 117 | 74 |
| 105. | 107. | 2414.53 | 2901.18 | 2415 | 2900 | 11.00103 | 11.99965 | 116 | 75 |
| 107. | 108. | 2901.18 | 3440.80 | 2901 | 3440 | 11.99965 | 13.00036 | 115 | 76 |
| 108. | 110. | 3440.80 | 4036.37 | 3441 | 4035 | 13.00036 | 13.99941 | 114 | 77 |
| 110. | 111. | 4036.37 | 4691.28 | 4036 | 4690 | 13.99941 | 14.99959 | 113 | 78 |
| 111. | 113. | 4691.28 | 5409.35 | 4691 | 5408 | 14.99959 | 15.99953 | 112 | 79 |
| 113. | 114. | 5409.35 | 6194.87 | 5409 | 6194 | 15.99953 | 17.00016 | 111 | 80 |
| 114. | 115. | 6194.87 | 7052.68 | 6195 | 7052 | 17.00016 | 18.00036 | 110 | 81 |
| 115. | 117. | 7052.68 | 7988.22 | 7053 | 7987 | 18.00036 | 18.99978 | 109 | 82 |
| 117. | 118. | 7988.22 | 9007.62 | 7988 | 9007 | 18.99978 | 20.00036 | 108 | 83 |
| 118. | 120. | 9007.62 | 10117.8 | 9008 | 10117 | 20.00036 | 21.00018 | 107 | 84 |
| 120. | 121. | 10117.8 | 11326.5 | 10118 | 11326 | 21.00018 | 22.00038 | 106 | 85 |
| 121. | 122. | 11326.5 | 12642.6 | 11327 | 12642 | 22.00038 | 23.00027 | 105 | 86 |
| 122. | 124. | 12642.6 | 14076.1 | 12643 | 14075 | 23.00027 | 23.99995 | 104 | 87 |
| 124. | 125. | 14076.1 | 15638.2 | 14076 | 15637 | 23.99995 | 24.99988 | 103 | 88 |
| 125. | 127. | 15638.2 | 17341.8 | 15638 | 17341 | 24.99988 | 26.00009 | 102 | 89 |
| 127. | 128. | 17341.8 | 19201.7 | 17342 | 19201 | 26.00009 | 27.00016 | 101 | 90 |
| 128. | 129. | 19201.7 | 21234.5 | 19202 | 21234 | 27.00016 | 28.00022 | 100 | 91 |
| 129. | 131. | 21234.5 | 23459.6 | 21235 | 23459 | 28.00022 | 29.00016 | 99 | 92 |
| 131. | 132. | 23459.6 | 25899.2 | 23460 | 25898 | 29.00016 | 29.99994 | 98 | 93 |

| | | | | | | | | | |
|------|------|---------|---------|-------|-------|----------|----------|-----|-----|
| 132. | 134. | 25899.2 | 28578.7 | 25899 | 28578 | 29.99994 | 31.00011 | 97 | 94 |
| 134. | 135 | 28578.7 | 31528 | 28579 | 31527 | 31.00011 | 32 | 96 | 95 |
| 135 | 136. | 31528 | 28578.7 | 31528 | 28578 | 32 | 31.00011 | 95 | 96 |
| 136. | 138. | 28578.7 | 25899.2 | 28579 | 25898 | 31.00011 | 29.99994 | 94 | 97 |
| 138. | 139. | 25899.2 | 23459.6 | 25899 | 23459 | 29.99994 | 29.00016 | 93 | 98 |
| 139. | 141. | 23459.6 | 21234.5 | 23460 | 21234 | 29.00016 | 28.00022 | 92 | 99 |
| 141. | 142. | 21234.5 | 19201.7 | 21235 | 19201 | 28.00022 | 27.00016 | 91 | 100 |
| 142. | 143. | 19201.7 | 17341.8 | 19202 | 17341 | 27.00016 | 26.00009 | 90 | 101 |
| 143. | 145. | 17341.8 | 15638.2 | 17342 | 15637 | 26.00009 | 24.99988 | 89 | 102 |
| 145. | 146. | 15638.2 | 14076.1 | 15638 | 14075 | 24.99988 | 23.99995 | 88 | 103 |
| 146. | 148. | 14076.1 | 12642.6 | 14076 | 12642 | 23.99995 | 23.00027 | 87 | 104 |
| 148. | 149. | 12642.6 | 11326.5 | 12643 | 11326 | 23.00027 | 22.00038 | 86 | 105 |
| 149. | 150. | 11326.5 | 10117.8 | 11327 | 10117 | 22.00038 | 21.00018 | 85 | 106 |
| 150. | 152. | 10117.8 | 9007.62 | 10118 | 9007 | 21.00018 | 20.00036 | 84 | 107 |
| 152. | 153. | 9007.62 | 7988.22 | 9008 | 7987 | 20.00036 | 18.99978 | 83 | 108 |
| 153. | 155. | 7988.22 | 7052.68 | 7988 | 7052 | 18.99978 | 18.00036 | 82 | 109 |
| 155. | 156. | 7052.68 | 6194.87 | 7053 | 6194 | 18.00036 | 17.00016 | 81 | 110 |
| 156. | 158. | 6194.87 | 5409.35 | 6195 | 5408 | 17.00016 | 15.99953 | 80 | 111 |
| 158. | 159. | 5409.35 | 4691.28 | 5409 | 4690 | 15.99953 | 14.99959 | 79 | 112 |
| 159. | 160. | 4691.28 | 4036.37 | 4691 | 4035 | 14.99959 | 13.99941 | 78 | 113 |
| 160. | 162. | 4036.37 | 3440.80 | 4036 | 3440 | 13.99941 | 13.00036 | 77 | 114 |
| 162. | 163. | 3440.80 | 2901.18 | 3441 | 2900 | 13.00036 | 11.99965 | 76 | 115 |
| 163. | 165. | 2901.18 | 2414.53 | 2901 | 2414 | 11.99965 | 11.00103 | 75 | 116 |
| 165. | 166. | 2414.53 | 1978.18 | 2415 | 1977 | 11.00103 | 9.999554 | 74 | 117 |
| 166. | 167. | 1978.18 | 1589.83 | 1978 | 1589 | 9.999554 | 9.000457 | 73 | 118 |
| 167. | 169. | 1589.83 | 1247.44 | 1590 | 1246 | 9.000457 | 7.998622 | 72 | 119 |
| 169. | 170. | 1247.44 | 949.244 | 1247 | 948 | 7.998622 | 6.999119 | 71 | 120 |
| 170. | 172. | 949.244 | 693.728 | 949 | 693 | 6.999119 | 6.001157 | 70 | 121 |
| 172. | 173. | 693.728 | 479.614 | 694 | 479 | 6.001157 | 5.001991 | 69 | 122 |
| 173. | 174. | 479.614 | 305.839 | 480 | 305 | 5.001991 | 4.001045 | 68 | 123 |
| 174. | 176. | 305.839 | 171.550 | 306 | 171 | 4.001045 | 3.003919 | 67 | 124 |
| 176. | 177. | 171.550 | 76.0912 | 172 | 75 | 3.003919 | 1.998803 | 66 | 125 |
| 177. | 179. | 76.0912 | 18.9999 | 76 | 18 | 1.998803 | 1.000003 | 65 | 126 |
| 179. | 180 | 18.9999 | 0 | 19 | 0 | 1.000003 | 0 | 64 | 127 |
| 180. | 181. | 0 | 18.9999 | 0 | 18 | 0 | 1.000003 | 128 | |
| 181. | 183. | 18.9999 | 76.0912 | 19 | 75 | 1.000003 | 1.998803 | 129 | |
| 183. | 184. | 76.0912 | 171.550 | 76 | 171 | 1.998803 | 3.003919 | 130 | |
| 184. | 186. | 171.550 | 305.839 | 172 | 305 | 3.003919 | 4.001045 | 131 | |
| 186. | 187. | 305.839 | 479.614 | 306 | 479 | 4.001045 | 5.001991 | 132 | |
| 187. | 188. | 479.614 | 693.728 | 480 | 693 | 5.001991 | 6.001157 | 133 | |
| 188. | 190. | 693.728 | 949.244 | 694 | 948 | 6.001157 | 6.999119 | 134 | |
| 190. | 191. | 949.244 | 1247.44 | 949 | 1246 | 6.999119 | 7.998622 | 135 | |
| 191. | 193. | 1247.44 | 1589.83 | 1247 | 1589 | 7.998622 | 9.000457 | 136 | |
| 193. | 194. | 1589.83 | 1978.18 | 1590 | 1977 | 9.000457 | 9.999554 | 137 | |
| 194. | 195. | 1978.18 | 2414.53 | 1978 | 2414 | 9.999554 | 11.00103 | 138 | |
| 195. | 197. | 2414.53 | 2901.18 | 2415 | 2900 | 11.00103 | 11.99965 | 139 | |
| 197. | 198. | 2901.18 | 3440.80 | 2901 | 3440 | 11.99965 | 13.00036 | 140 | |
| 198. | 200. | 3440.80 | 4036.37 | 3441 | 4035 | 13.00036 | 13.99941 | 141 | |
| 200. | 201. | 4036.37 | 4691.28 | 4036 | 4690 | 13.99941 | 14.99959 | 142 | |
| 201. | 203. | 4691.28 | 5409.35 | 4691 | 5408 | 14.99959 | 15.99953 | 143 | |
| 203. | 204. | 5409.35 | 6194.87 | 5409 | 6194 | 15.99953 | 17.00016 | 144 | |
| 204. | 205. | 6194.87 | 7052.68 | 6195 | 7052 | 17.00016 | 18.00036 | 145 | |
| 205. | 207. | 7052.68 | 7988.22 | 7053 | 7987 | 18.00036 | 18.99978 | 146 | |
| 207. | 208. | 7988.22 | 9007.62 | 7988 | 9007 | 18.99978 | 20.00036 | 147 | |

| | | | | | | | | |
|------|------|---------|---------|-------|-------|----------|----------|-----|
| 208. | 210. | 9007.62 | 10117.8 | 9008 | 10117 | 20.00036 | 21.00018 | 148 |
| 210. | 211. | 10117.8 | 11326.5 | 10118 | 11326 | 21.00018 | 22.00038 | 149 |
| 211. | 212. | 11326.5 | 12642.6 | 11327 | 12642 | 22.00038 | 23.00027 | 150 |
| 212. | 214. | 12642.6 | 14076.1 | 12643 | 14075 | 23.00027 | 23.99995 | 151 |
| 214. | 215. | 14076.1 | 15638.2 | 14076 | 15637 | 23.99995 | 24.99988 | 152 |
| 215. | 217. | 15638.2 | 17341.8 | 15638 | 17341 | 24.99988 | 26.00009 | 153 |
| 217. | 218. | 17341.8 | 19201.7 | 17342 | 19201 | 26.00009 | 27.00016 | 154 |
| 218. | 219. | 19201.7 | 21234.5 | 19202 | 21234 | 27.00016 | 28.00022 | 155 |
| 219. | 221. | 21234.5 | 23459.6 | 21235 | 23459 | 28.00022 | 29.00016 | 156 |
| 221. | 222. | 23459.6 | 25899.2 | 23460 | 25898 | 29.00016 | 29.99994 | 157 |
| 222. | 224. | 25899.2 | 28578.7 | 25899 | 28578 | 29.99994 | 31.00011 | 158 |
| 224. | 225 | 28578.7 | 31528 | 28579 | 31527 | 31.00011 | 32 | 159 |
| 225 | 226. | 31528 | 28578.7 | 31528 | 28578 | 32 | 31.00011 | 160 |
| 226. | 228. | 28578.7 | 25899.2 | 28579 | 25898 | 31.00011 | 29.99994 | 161 |
| 228. | 229. | 25899.2 | 23459.6 | 25899 | 23459 | 29.99994 | 29.00016 | 162 |
| 229. | 231. | 23459.6 | 21234.5 | 23460 | 21234 | 29.00016 | 28.00022 | 163 |
| 231. | 232. | 21234.5 | 19201.7 | 21235 | 19201 | 28.00022 | 27.00016 | 164 |
| 232. | 233. | 19201.7 | 17341.8 | 19202 | 17341 | 27.00016 | 26.00009 | 165 |
| 233. | 235. | 17341.8 | 15638.2 | 17342 | 15637 | 26.00009 | 24.99988 | 166 |
| 235. | 236. | 15638.2 | 14076.1 | 15638 | 14075 | 24.99988 | 23.99995 | 167 |
| 236. | 238. | 14076.1 | 12642.6 | 14076 | 12642 | 23.99995 | 23.00027 | 168 |
| 238. | 239. | 12642.6 | 11326.5 | 12643 | 11326 | 23.00027 | 22.00038 | 169 |
| 239. | 240. | 11326.5 | 10117.8 | 11327 | 10117 | 22.00038 | 21.00018 | 170 |
| 240. | 242. | 10117.8 | 9007.62 | 10118 | 9007 | 21.00018 | 20.00036 | 171 |
| 242. | 243. | 9007.62 | 7988.22 | 9008 | 7987 | 20.00036 | 18.99978 | 172 |
| 243. | 245. | 7988.22 | 7052.68 | 7988 | 7052 | 18.99978 | 18.00036 | 173 |
| 245. | 246. | 7052.68 | 6194.87 | 7053 | 6194 | 18.00036 | 17.00016 | 174 |
| 246. | 248. | 6194.87 | 5409.35 | 6195 | 5408 | 17.00016 | 15.99953 | 175 |
| 248. | 249. | 5409.35 | 4691.28 | 5409 | 4690 | 15.99953 | 14.99959 | 176 |
| 249. | 250. | 4691.28 | 4036.37 | 4691 | 4035 | 14.99959 | 13.99941 | 177 |
| 250. | 252. | 4036.37 | 3440.80 | 4036 | 3440 | 13.99941 | 13.00036 | 178 |
| 252. | 253. | 3440.80 | 2901.18 | 3441 | 2900 | 13.00036 | 11.99965 | 179 |
| 253. | 255. | 2901.18 | 2414.53 | 2901 | 2414 | 11.99965 | 11.00103 | 180 |
| 255. | 256. | 2414.53 | 1978.18 | 2415 | 1977 | 11.00103 | 9.99954 | 181 |
| 256. | 257. | 1978.18 | 1589.83 | 1978 | 1589 | 9.99954 | 9.000457 | 182 |
| 257. | 259. | 1589.83 | 1247.44 | 1590 | 1246 | 9.000457 | 7.998622 | 183 |
| 259. | 260. | 1247.44 | 949.244 | 1247 | 948 | 7.998622 | 6.999119 | 184 |
| 260. | 262. | 949.244 | 693.728 | 949 | 693 | 6.999119 | 6.001157 | 185 |
| 262. | 263. | 693.728 | 479.614 | 694 | 479 | 6.001157 | 5.001991 | 186 |
| 263. | 264. | 479.614 | 305.839 | 480 | 305 | 5.001991 | 4.001045 | 187 |
| 264. | 266. | 305.839 | 171.550 | 306 | 171 | 4.001045 | 3.003919 | 188 |
| 266. | 267. | 171.550 | 76.0912 | 172 | 75 | 3.003919 | 1.998803 | 189 |
| 267. | 269. | 76.0912 | 18.9999 | 76 | 18 | 1.998803 | 1.000003 | 190 |
| 269. | 270 | 18.9999 | 0 | 19 | 0 | 1.000003 | 0 | 191 |
| 270. | 271. | 0 | 18.9999 | 0 | 18 | 0 | 1.000003 | 192 |
| 271. | 273. | 18.9999 | 76.0912 | 19 | 75 | 1.000003 | 1.998803 | 193 |
| 273. | 274. | 76.0912 | 171.550 | 76 | 171 | 1.998803 | 3.003919 | 194 |
| 274. | 276. | 171.550 | 305.839 | 172 | 305 | 3.003919 | 4.001045 | 195 |
| 276. | 277. | 305.839 | 479.614 | 306 | 479 | 4.001045 | 5.001991 | 196 |
| 277. | 278. | 479.614 | 693.728 | 480 | 693 | 5.001991 | 6.001157 | 197 |
| 278. | 280. | 693.728 | 949.244 | 694 | 948 | 6.001157 | 6.999119 | 198 |
| 280. | 281. | 949.244 | 1247.44 | 949 | 1246 | 6.999119 | 7.998622 | 199 |
| 281. | 283. | 1247.44 | 1589.83 | 1247 | 1589 | 7.998622 | 9.000457 | 200 |
| 283. | 284. | 1589.83 | 1978.18 | 1590 | 1977 | 9.000457 | 9.999554 | 201 |

| | | | | | | | | |
|------|------|---------|---------|-------|-------|----------|----------|-----|
| 284. | 285. | 1978.18 | 2414.53 | 1978 | 2414 | 9.999554 | 11.00103 | 202 |
| 285. | 287. | 2414.53 | 2901.18 | 2415 | 2900 | 11.00103 | 11.99965 | 203 |
| 287. | 288. | 2901.18 | 3440.80 | 2901 | 3440 | 11.99965 | 13.00036 | 204 |
| 288. | 290. | 3440.80 | 4036.37 | 3441 | 4035 | 13.00036 | 13.99941 | 205 |
| 290. | 291. | 4036.37 | 4691.28 | 4036 | 4690 | 13.99941 | 14.99959 | 206 |
| 291. | 293. | 4691.28 | 5409.35 | 4691 | 5408 | 14.99959 | 15.99953 | 207 |
| 293. | 294. | 5409.35 | 6194.87 | 5409 | 6194 | 15.99953 | 17.00016 | 208 |
| 294. | 295. | 6194.87 | 7052.68 | 6195 | 7052 | 17.00016 | 18.00036 | 209 |
| 295. | 297. | 7052.68 | 7988.22 | 7053 | 7987 | 18.00036 | 18.99978 | 210 |
| 297. | 298. | 7988.22 | 9007.62 | 7988 | 9007 | 18.99978 | 20.00036 | 211 |
| 298. | 300. | 9007.62 | 10117.8 | 9008 | 10117 | 20.00036 | 21.00018 | 212 |
| 300. | 301. | 10117.8 | 11326.5 | 10118 | 11326 | 21.00018 | 22.00038 | 213 |
| 301. | 302. | 11326.5 | 12642.6 | 11327 | 12642 | 22.00038 | 23.00027 | 214 |
| 302. | 304. | 12642.6 | 14076.1 | 12643 | 14075 | 23.00027 | 23.99995 | 215 |
| 304. | 305. | 14076.1 | 15638.2 | 14076 | 15637 | 23.99995 | 24.99988 | 216 |
| 305. | 307. | 15638.2 | 17341.8 | 15638 | 17341 | 24.99988 | 26.00009 | 217 |
| 307. | 308. | 17341.8 | 19201.7 | 17342 | 19201 | 26.00009 | 27.00016 | 218 |
| 308. | 309. | 19201.7 | 21234.5 | 19202 | 21234 | 27.00016 | 28.00022 | 219 |
| 309. | 311. | 21234.5 | 23459.6 | 21235 | 23459 | 28.00022 | 29.00016 | 220 |
| 311. | 312. | 23459.6 | 25899.2 | 23460 | 25898 | 29.00016 | 29.99994 | 221 |
| 312. | 314. | 25899.2 | 28578.7 | 25899 | 28578 | 29.99994 | 31.00011 | 222 |
| 314. | 315. | 28578.7 | 31528 | 28579 | 31527 | 31.00011 | 32 | 223 |
| 315. | 316. | 31528 | 28578.7 | 31528 | 28578 | 32 | 31.00011 | 224 |
| 316. | 318. | 28578.7 | 25899.2 | 28579 | 25898 | 31.00011 | 29.99994 | 225 |
| 318. | 319. | 25899.2 | 23459.6 | 25899 | 23459 | 29.99994 | 29.00016 | 226 |
| 319. | 321. | 23459.6 | 21234.5 | 23460 | 21234 | 29.00016 | 28.00022 | 227 |
| 321. | 322. | 21234.5 | 19201.7 | 21235 | 19201 | 28.00022 | 27.00016 | 228 |
| 322. | 323. | 19201.7 | 17341.8 | 19202 | 17341 | 27.00016 | 26.00009 | 229 |
| 323. | 325. | 17341.8 | 15638.2 | 17342 | 15637 | 26.00009 | 24.99988 | 230 |
| 325. | 326. | 15638.2 | 14076.1 | 15638 | 14075 | 24.99988 | 23.99995 | 231 |
| 326. | 328. | 14076.1 | 12642.6 | 14076 | 12642 | 23.99995 | 23.00027 | 232 |
| 328. | 329. | 12642.6 | 11326.5 | 12643 | 11326 | 23.00027 | 22.00038 | 233 |
| 329. | 330. | 11326.5 | 10117.8 | 11327 | 10117 | 22.00038 | 21.00018 | 234 |
| 330. | 332. | 10117.8 | 9007.62 | 10118 | 9007 | 21.00018 | 20.00036 | 235 |
| 332. | 333. | 9007.62 | 7988.22 | 9008 | 7987 | 20.00036 | 18.99978 | 236 |
| 333. | 335. | 7988.22 | 7052.68 | 7988 | 7052 | 18.99978 | 18.00036 | 237 |
| 335. | 336. | 7052.68 | 6194.87 | 7053 | 6194 | 18.00036 | 17.00016 | 238 |
| 336. | 338. | 6194.87 | 5409.35 | 6195 | 5408 | 17.00016 | 15.99953 | 239 |
| 338. | 339. | 5409.35 | 4691.28 | 5409 | 4690 | 15.99953 | 14.99959 | 240 |
| 339. | 340. | 4691.28 | 4036.37 | 4691 | 4035 | 14.99959 | 13.99941 | 241 |
| 340. | 342. | 4036.37 | 3440.80 | 4036 | 3440 | 13.99941 | 13.00036 | 242 |
| 342. | 343. | 3440.80 | 2901.18 | 3441 | 2900 | 13.00036 | 11.99965 | 243 |
| 343. | 345. | 2901.18 | 2414.53 | 2901 | 2414 | 11.99965 | 11.00103 | 244 |
| 345. | 346. | 2414.53 | 1978.18 | 2415 | 1977 | 11.00103 | 9.999554 | 245 |
| 346. | 347. | 1978.18 | 1589.83 | 1978 | 1589 | 9.999554 | 9.000457 | 246 |
| 347. | 349. | 1589.83 | 1247.44 | 1590 | 1246 | 9.000457 | 7.998622 | 247 |
| 349. | 350. | 1247.44 | 949.244 | 1247 | 948 | 7.998622 | 6.999119 | 248 |
| 350. | 352. | 949.244 | 693.728 | 949 | 693 | 6.999119 | 6.001157 | 249 |
| 352. | 353. | 693.728 | 479.614 | 694 | 479 | 6.001157 | 5.001991 | 250 |
| 353. | 354. | 479.614 | 305.839 | 480 | 305 | 5.001991 | 4.001045 | 251 |
| 354. | 356. | 305.839 | 171.550 | 306 | 171 | 4.001045 | 3.003919 | 252 |
| 356. | 357. | 171.550 | 76.0912 | 172 | 75 | 3.003919 | 1.998803 | 253 |
| 357. | 359. | 76.0912 | 18.9999 | 76 | 18 | 1.998803 | 1.000003 | 254 |
| 359. | 360. | 18.9999 | 0 | 19 | 0 | 1.000003 | 0 | 255 |

GRID FOR UP SIDE DOWN DETECTOR A

Dots represent pixel centers. Use 132 columns to print this table.

File C:\HYDRA\PAS\GRIDABAB.COD, June 17, 1992

PHI PHI PHI PHI

Degrees Measured from Xs/c

Elec. Look BINARY GRAYGRAY

Velo. Dir. CODE CODECODE

. 264.5 84.5 00000 00000 0

. 263.5 83.5 00001 00001 1

. 262.5 82.5 00010 00011 3

. 261.5 81.5 00011 00010 2

. 260.5 80.5 00100 00110 6

. 259.5 79.5 00101 00111 7

. 258.5 78.5 00110 00101 5

. 257.5 77.5 00111 00100 4

. 256.5 76.5 01000 01100 C

. 255.5 75.5 01001 01101 D

. 254.5 74.5 01010 01111 F

. 253.5 73.5 01011 01110 E

. 252.5 72.5 01100 01010 A

. 251.5 71.5 01101 01011 B

. 250.5 70.5 01110 01001 9

. 249.5 69.5 01111 01000 8

. ><. 248.5 68.5 10000 11000 18

. 247.5 67.5 10001 11001 19

. 246.5 66.5 10010 11011 1B

. 245.5 65.5 10011 11010 1A

. 244.5 64.5 10100 11110 1E

. 243.5 63.5 10101 11111 1F

. 242.5 62.5 10110 11101 1D

. 241.5 61.5 10111 11100 1C

. 240.5 60.5 11000 10100 14

. 239.5 59.5 11001 10101 15

. 238.5 58.5 11010 10111 17

. 237.5 57.5 11011 10110 16

. 236.5 56.5 11100 10010 12

. 235.5 55.5 11101 10011 13

. 234.5 54.5 11110 10001 11

. 233.5 53.5 11111 10000 10

1 1 1 1 1 1 E V THETA

7 7 7 7 7 7 8 8 8 8 8 8 8 9 9 9 9 9 9 9 9 9 9 9 9 0 0 0 0 0 0 L E

4 5 6 7 8 9 0 1 2 3 4 5 6 7 8 9 0 1 2 3 4 5 6 7 8 9 0 1 2 3 4 5 E L Velocity Vector

. C O Measured from

5 Zs/c

1 1 1 1 1 1 L THETA

0 0 0 0 0 0 9 9 9 9 9 9 9 9 9 9 8 8 8 8 8 8 8 8 8 7 7 7 7 7 7 7 0 0 D

5 4 3 2 1 0 9 8 7 6 5 4 3 2 1 0 9 8 7 6 5 4 3 2 1 0 9 8 7 6 5 4 0 1 I Look Direction

. K R Measured from

5 Zs/c

1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 B

1 1 1 1 1 1 1 0 0 0 0 0 0 0 0 0 1 1 1 1 1 1 1 0 0 0 0 0 0 0 0 0 0 0 1 C

1 1 1 1 0 0 0 0 1 1 1 1 0 0 0 0 0 1 1 1 1 0 0 0 0 1 1 1 1 1 0 0 0 0 N 0

1 1 0 0 1 1 0 0 1 1 0 0 1 1 0 0 1 1 0 0 1 1 0 0 1 1 0 0 1 1 0 0 A D

1 0 1 0 1 0 1 0 1 0 1 0 1 0 1 0 1 0 1 0 1 0 1 0 1 0 1 0 1 0 1 0 R E

Y

1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 G C THETA

0 0 0 0 0 0 0 0 1 R O

0 0 0 0 1 1 1 1 1 1 1 1 0 0 0 0 0 0 0 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 A D

0 0 1 1 1 1 0 0 0 0 1 1 1 1 0 0 0 0 1 1 1 1 1 0 0 0 0 1 1 1 1 1 1 1 1 1 0 0 Y E

0 1 1 0 0 1 1 0 0 1 1 0 0 1 1 0 0 1 1 0 0 1 1 0 0 1 1 0 0 1 1 0 0 1 1 0 0 G C

R O

1 A D

0 1 3 2 6 7 5 4 C D F E A B 9 8 8 9 B A E F D C 4 5 7 6 2 3 1 0 Y E

GRID FOR RIGHT SIDE UP DETECTOR B

Dots represent pixel centers. Use 132 columns to print this table.

File C:\HYDRA\PAS\GRIDABAB.COD, June 17, 1992

PHI PHI PHI PHI

Degrees Measured from Xs/c

Elec. Look BINARY GRAYGRAY

Velo. Dir. CODE CODECODE

. 53.5 233.5 00000 00000 0

. 54.5 234.5 00001 00001 1

. 55.5 235.5 00010 00011 3

. 56.5 236.5 00011 00010 2

. 57.5 237.5 00100 00110 6

. 58.5 238.5 00101 00111 7

. 59.5 239.5 00110 00101 5

. 60.5 240.5 00111 00100 4

. 61.5 241.5 01000 01100 C

. 62.5 242.5 01001 01101 D

. 63.5 243.5 01010 01111 F

. 64.5 244.5 01011 01110 E

. 65.5 245.5 01100 01010 A

. 66.5 246.5 01101 01011 B

. 67.5 247.5 01110 01001 9

. 68.5 248.5 01111 01000 8

>< 69.5 249.5 10000 11000 18

. 70.5 250.5 10001 11001 19

. 71.5 251.5 10010 11011 1B

. 72.5 252.5 10011 11010 1A

. 73.5 253.5 10100 11110 1E

. 74.5 254.5 10101 11111 1F

. 75.5 255.5 10110 11101 1D

. 76.5 256.5 10111 11100 1C

. 77.5 257.5 11000 10100 14

. 78.5 258.5 11001 10101 15

. 79.5 259.5 11010 10111 17

. 80.5 260.5 11011 10110 16

. 81.5 260.5 11100 10010 12

. 82.5 262.5 11101 10011 13

. 83.5 263.5 11110 10001 11

. 84.5 264.5 11111 10000 10

1 1 1 1 1 1

E V THETA

0 0 0 0 0 9 9 9 9 9 9 9 9 9 8 8 8 8 8 8 8 8 8 7 7 7 7 7 7 7

L E

5 4 3 2 1 0 9 8 7 6 5 4 3 2 1 0 9 8 7 6 5 4 3 2 1 0 9 8 7 6 5 4

E L Velocity Vector

. .

C O Measured from

5 5

Zs/c

1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 L THETA

7 7 7 7 7 7 7 8 8 8 8 8 8 8 8 8 8 9 9 9 9 9 9 9 9 9 9 0 0 0 0 0 0 0

O D

4 5 6 7 8 9 0 1 2 3 4 5 6 7 8 9 0 1 2 3 4 5 6 7 8 9 0 1 2 3 4 5 0 I Look Direction

. .

K R Measured from

5 5

Zs/c

1 B

1 I C

1 1 1 1 0 0 0 0 1 1 1 1 0 0 0 0 1 1 1 1 0 0 0 0 1 1 1 1 0 0 0 0 1 1 1 1 N O

1 1 0 0 1 1 0 0 1 1 0 0 1 1 0 0 1 1 0 0 1 1 0 0 1 1 0 0 1 1 0 0 1 1 0 0 A D

1 0 1 0 1 0 1 0 1 0 1 0 1 0 1 0 1 0 1 0 1 0 1 0 1 0 1 0 1 0 1 0 1 0 1 0 R E

1 G C THETA

0 0 0 0 0 0 0 1 R O

0 0 0 0 1 1 1 1 1 1 1 0 0 0 0 0 0 0 0 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 A D

0 0 1 1 1 1 0 0 0 0 1 1 1 1 0 0 0 0 1 1 1 1 1 1 0 0 0 0 1 1 1 1 1 1 1 1 Y E

0 1 1 0 0 1 1 0 0 1 1 0 0 1 1 0 0 1 1 0 0 1 1 0 0 1 1 0 0 1 1 0 0 1 1 0 0 G C

R O

1 A D

0 1 3 2 6 7 5 4 C D F E A B 9 8 8 9 B A E F D C 4 5 7 6 2 3 1 0 Y E

HVMON_3.0. DDEIS and PPA High Voltage Monitoring
September 29, 1996

HVMON_3.1. The Design Problem in HV Monitoring

The code described here monitors the deflection HV levels directly through a 10-bit A/D converter, and performs this task in the background during normal scientific operation of the instrument. Note that we don't want to sample the HV when it is on a transient; and we don't want our HV sampling period to be commensurate with the scan sequence in such a way as to repeat some samples without getting the others. In order to solve these timing problems, the scan program (DDSCAN and PPSCAN) controls the timing of the sample.

To avoid transients, the sample is requested on the second BCI of a HV step, assuming each HV step is two or more BCI's long.

In order to sample every possible level, the HV monitor code in the scan program steps slowly through all 256 permutations of a byte and seeks a match with the current HV control byte. The HV monitor dwells on each permutation for 8 MJF's for the DDEIS and 32 MJF's for the PPA, in order to cover a complete scan of all available values. Thus it takes 5.2 hours to complete a cycle of every possible level for the DDEIS, and 20.9 hours for the PPA. Note that some HV levels may not be available if they are not included in the scan sequence; in this case the telemetry returns all bits on. For levels that occur more than once during a search, only the first occurrence is recorded, and the A/D converter is not exercised subsequently.

HVMON_3.2. Overview

The DDSCAN and PPSCAN routines will periodically ask the BCI ISR to sample the Analog to Digital converter to get the value of the high voltage for their respective instruments. In each case, the values returned consist of four bytes, with bits 0-9 of each of the two-byte words containing the 10-bit readback from one of the sides of the instrument. We don't know which of the four bytes are from which side of the instrument, but we presume Jerry Needell knows.

HVMON_3.3. Code in DDSCAN and PPSCAN:

The following discussion applies to both the DDEIS and the PPA. Where there are differences between the instruments, the main text is for the DDEIS, and changes for the PPA are given in square brackets.

After power-up or a new descriptor command, initialization for HV monitoring is performed. This consists of

saving bits 3-10 [PPA: 5-12] of the major frame count as the HV control byte value to watch for. Pointers are set to the scan and telemetry halves of a readback double buffer, the scan half is cleared, and the telemetry half is set to an invalid value by turning all bits on.

At the start of the scan routine when not initializing, the major frame count is first checked to see if it is time to begin looking for a new HV value. If it is, a 'match-found' flag is checked (and simultaneously cleared) to see if there has been a match on the old value. If there has not, the scan readback buffer is set to all ones indicating invalid. Next, whether or not there has been a match, the scan and telemetry pointers to the readback buffer are swapped, and the new scan half is cleared.

If no match has yet been found on the present value being sought, it is compared to the HV control byte representing the value to which the instrument has just been set. If they are the same, a flag is set telling the BCI ISR to do the A-to-D conversion the next time it runs, and the 'match found' flag is set.

HVMON_3.4. Code in the telemetry task:

In the 'sub1' routine of the telemetry task, which executes in the third quarter of the major frame, a single byte of the HV readback values is copied to the science housekeeping loose byte buffer, byte 135; the data analyst must assemble four occurrences of byte 135 from 4 MJF's in order to make a complete sample. In assembling samples, bits 0-2 of the major frame counter determine which byte it is. When bit 2 is 0, the byte is from the ddeis, and when it is 1, it is from the ppa. In either case, the other two bits indicate which byte it is of the four returned by the BCI ISR, with 00 being the byte with the lowest address, and 11 the highest.

PHA_3.0. Pulse Height Analysis
September 29, 1996

Pulse height analysis is accomplished by code distributed through the MJF ISR, DDSCAN routine, and TLMTASK task. The sequencer is a triple-nested loop taking 8 or 9 hours to complete. The loop heirarchy is:

- (i) Deflection HV: 32 foreground levels + 1 background level
- (ii) CEM #: 12 pairs
- (iii) Discrimination level: 16 levels

The outer, or slowest, loop scans through the HV deflection levels in 32 steps. The steps are specified in detail in Section PHA 3.5. below. The background loop uses any HV level which has polarity opposite to that of the CEM.

The middle loop scans through the 12 CEM's in each of the 2 EIS pods, 6 ion CEM's and 6 electron CEM's. The two pods are handled simultaneously so that each CEM is paired with its opposite.

The inner loop scans the levels of the PHA discriminator. Although the discriminator provides 256 levels, 16 seem enough. Again, the desired levels are named in a lookup table, which can be reloaded by ground command if desired.

PHA_3.1. Code in TLMTASK

Each quarter of an MJF, TLMTASK must collect part of the PHA data and the science housekeeping data and insert them into the appropriate telemetry buffers. PHA data occur in the following bytes of the loose bytes telemetry: offsets 12-15, 29-32, 46-49, and 63-65. See TLMF.TLMLB_3. for an enumeration of the loose bytes housekeeping telemetry.

PHA_3.2. Code in the MJF ISR

The MJF ISR picks up the PHA selection vector prepared by DDSCAN, and immediately sets the new discrimination level by writing to the DPUII (the same for both EIS's). It also writes to the DPUII whenever a flag indicates that there is a change in CEM selection, to attach the PHA discriminator to the new CEM.

PHA_3.3. Code in DDSCAN

The first run of DDSCAN in each MJF creates the PHA selection vector for the next major frame interval. If the CEM selection has changed, a flag is set for the MJF ISR.

Each time the accumulators are read out, DDSCAN checks the associated "was" CEM polarity against the PHA CEM selection polarity. If they match, DDSCAN compares the deflection HV as

detailed in PHA_3.5. If they match, DDSCAN keeps the accumulator readouts for both the two PHA discriminators (one from each EIS), and also from the two matching duty accumulators. These readings are replace-added into four 32-bit words in the DDSCAN half of a double buffer shared with TLMTASK. At the beginning of each MJF, the DDSCAN and TLMTASK pointers to this buffer are swapped, and the DDSCAN portion of the buffer is zeroed. For instance, in a scan identical to one in ModeZero, with 8 ion scans and 8 electron scans per MJF, the result at the end of the MJF will be the sum of the accumulations from 8 occurrences of the matching inputs. In other modes the number of accumulations producing a match may vary.

PHA_3.4. PHA Input Selection

On each side a single A111 PHA amplifier is fed through a MUX by the analog signal output of 12 A150 preamps belonging to the individual electron multipliers (CEM's). Selection of the PHA channel is done by poking a 16 bit serial input word through the DPUII interface as described in the DPUII address map. The 16 bit word consists of an 8 bit address and an 8 bit instruction. The high nibble of the instruction byte selects the PHA channel, and the low nibble selects the A/D converter channel. Note that, when selecting either the A/D converter input or the PHA input, one must remember and preserve the input to the other MUX in the other nibble. The following table tells the CEM channels selected by each value of the PHA nibble.

| PHA selection nibble | Side 1 top of top shelf | Side 2 bot of bot shelf | Accumulator offset | |
|-------------------------|-------------------------------|-------------------------------|-----------------------|--------|
| | | | Side 1 | Side 2 |
| 0X | E1 | E2 | 0 | 7 |
| 2X | E3 | E4 | 2 | 9 |
| 4X | E5 | E6 | 4 | B |
| 8X | E7 | E8 | 6 | 1 |
| AX | E9 | E10 | A | 5 |
| CX | E11 | E12 | 8 | 3 |
| | PHA output | PHA output | C | D |
| 1X | I1 | I2 | 0 | 7 |
| 3X | I3 | I4 | 2 | 9 |
| 5X | I5 | I6 | 4 | B |
| 9X | I7 | I8 | 6 | 1 |
| BX | I9 | I10 | A | 5 |
| DX | I11 | I12 | 8 | 3 |
| | PHA output | PHA output | C | D |

Nibbles 6X, 7X, EX, and FX are not used, and these inputs to the MUX are connected to ground.

The outputs of the 12 active A150 preamp/discriminators are fed to the 82C54 registers, and the outputs of these registers are collected once per DDC and appear as a stack of 12 16 bit words for collection by the telemetry task. The output

of the PHA registers also appear as the thirteenth and fourteenth words on the stack. The above table gives the offset into the table for the accumulators attached to each of the input CEM's, and discloses which of the A150's is matched to any selected input to the A111's.

One of the objectives of our background PHA scheme is to collect the outputs of the A111 PHA preamps and the matched A150 preamps simultaneously for comparison. The above table gives the information needed to make the match. The above information was drawn from Jerry Needell's "Hydra CEM - Accumulator Map" of 4/11/93, and from Jim Lobell's checkout command file described as "AMP1_CHK.ICL, 10:39 AM, 6/4/93". They are stored in directory c:/hydra/fid_3 as files "CEMMAP PHA 3284
12-29-93 4:19p", and "LOBELFIL PHA 10010 12-21-93
11:30a".

In the above table, the CEM's are designated by an alphabetic character, E or I, and a number, 1-12. E or I obviously designates electrons or ions, and the number selects the analyzers. Jim Lobell has assured me that the analyzer designation is the same used in the mechanical drawings and used by Jack Scudder.

PHA_3.5. Deflection Voltage Selection

The outer, or slowest, loop scans through the HV deflection levels in 32 steps. Eight levels of ion data, and 24 levels of electron data, for a total of 32 levels when you add together the two polarities. The asymmetry is because the 2000 v post-analysis acceleration on the ion side gives the lowest energies analyzed nearly the same energy at the CEM. Although there are more HV levels for each polarity, the CEM response is not expected to differ enough from step to step to require that much resolution. Eight and 24 steps are enough.

The match criteria used by the DDSCAN code for the HV deflection steps should be loaded into a table of depth 32 (or, if you please, two tables of depth 8 and 24.) The contents of the table can be varied by ground command to provide some flexibility. Each entry of the table should be a byte with the 2 lsb's equal to zero. This is compared with a byte formed from the 6 msb's of the HV control byte and 2 zero lsb's. Thus only the 6 msb's of the HV control byte count in making the match, and so any of 4 deflection levels within 3 steps (50% in energy) above the nominal level is accepted. The following are the deflection supply levels that will be the targets for PHA analysis. These values are based on calibration data from the SN001 supplies taken at ambient temperature, Sept-Oct, 1992.

PHA_3.5.1. Electron CEM's: 24 Levels

Positive Deflection Polarity, Low Range

| Pos | Range | | Control | HV | Log |
|-----|--------|-------|---------|--------|---------|
| Neg | Select | Level | HexByte | A-B | ABS(HV) |
| 0 | 0 | 60 | 3C | -13.23 | 1.12 |
| 0 | 0 | 56 | 38 | -7.58 | 0.880 |
| 0 | 0 | 52 | 34 | -4.41 | 0.644 |
| 0 | 0 | 48 | 30 | -2.48 | 0.394 |
| 0 | 0 | 44 | 2C | -1.43 | 0.155 |
| 0 | 0 | 40 | 28 | -0.76 | -0.12 |
| 0 | 0 | 36 | 24 | -0.39 | -0.41 |
| 0 | 0 | 32 | 20 | -0.17 | -0.77 |
| 0 | 0 | 28 | 1C | -0.07 | -1.2 |

Positive Polarity, High Range

| Pos | Range | | Control | HV | Log |
|-----|--------|-------|---------|----------|---------|
| Neg | Select | Level | HexByte | A-B | ABS(HV) |
| 0 | 1 | 60 | 7C | -6669.12 | 3.82 |
| 0 | 1 | 56 | 78 | -3844.85 | 3.58 |
| 0 | 1 | 52 | 74 | -2268.57 | 3.36 |
| 0 | 1 | 48 | 70 | -1305.91 | 3.12 |
| 0 | 1 | 44 | 6C | -772.04 | 2.89 |
| 0 | 1 | 40 | 68 | -444.39 | 2.65 |
| 0 | 1 | 36 | 64 | -262.60 | 2.42 |
| 0 | 1 | 32 | 60 | -151.16 | 2.18 |
| 0 | 1 | 28 | 5C | -89.59 | 1.95 |
| 0 | 1 | 24 | 58 | -51.56 | 1.71 |
| 0 | 1 | 20 | 54 | -30.46 | 1.48 |
| 0 | 1 | 16 | 50 | -17.52 | 1.24 |
| 0 | 1 | 12 | 4C | -10.37 | 1.02 |
| 0 | 1 | 8 | 48 | -5.96 | 0.775 |
| 0 | 1 | 4 | 44 | -3.49 | 0.543 |

PHA_3.5.2. Ion CEM's: 8 Levels

Negative Deflection Polarity, High Range

| Pos | Range | | Control | HV | Log | Ion Energy |
|-----|--------|-------|---------|---------|---------|------------|
| Neg | Select | Level | HexByte | A-B | ABS(HV) | at CEM, eV |
| 1 | 1 | 36 | E4 | 266.13 | 2.43 | 2941 |
| 1 | 1 | 40 | E8 | 450.22 | 2.65 | 3592 |
| 1 | 1 | 44 | EC | 782.43 | 2.89 | 4766 |
| 1 | 1 | 48 | F0 | 1323.89 | 3.12 | 6680 |
| 1 | 1 | 52 | F4 | 2300.28 | 3.36 | 10131 |
| 1 | 1 | 56 | F8 | 3900.00 | 3.59 | 15787 |
| 1 | 1 | 60 | FC | 6771.07 | 3.83 | 25936 |

Negative Deflection Polarity, Low Range

| Pos | Range | Control | HV | Log |
|-----|-------|---------|----|-----|
|-----|-------|---------|----|-----|

| Neg | Select | Level | HexByte | A-B | ABS(HV) |
|-----|--------|-------|---------|------|---------|
| 1 | 0 | 44 | AC | 1.70 | 0.230 |
| | | | | | 2006 |

Remember that a command byte has negative polarity if MSB=1, and yields deflection voltages that analyze for positive particles. This follows because side A is connected to the outer plate. The step size on the log(HV) scale approximates a uniform 0.06 across both ranges, and the step size for PHA selection is typically 4 levels, or a nominal 0.24 on the log(HV) scale.

TLM_0.0 Hydra ModeZero Task TLM_0
September 29, 1996

Takes data from the holding-processing buffers, packs them, and writes the packed data into the telemetry buffer. Task TLM_0 must not read data until after PPSCAN_0 and DDSCAN_0 have completed filling half of their holding-processing buffers PP16_BUF and DD16_BUF, and it must not write data into the telemetry buffer until the telemetry task has cleared the last half. To assure these conditions, TLM_0 is started 4 times per MJF by PPSCAN_0 8 BCI's after at the end of each PPC. TLM_0 must complete by the end of the next PPC. It fills TMBUF in the order of 256 bytes (PPTPV), 150 bytes (PPTMBINS), 960 bytes (DDTM), and 4 or 3 remaining bytes for even and odd quarters, respectively. The following subtasks describe the task in more detail.

TLM_0.1. PP2TM

The PPA data for each PPC consists of 256 16-bit accumulations saved in a double buffer, PP16BUF, of length 1024 bytes. At the end of each accumulation, these 256 bins are mapped, or rebinned, into 120 bins, and compressed PSRL 16 to 10 into 150 bytes in the telemetry buffer PPTMBINS. In case of overflow in the rebinning operation, a flag, PPAOV2, will be set.

There is also sector information generated throughout the scan, consisting of 128 sectors of 2 bytes each, where the 2 bytes are 1 overflow bit, 7 theta bits, and 8 phi bits. These data are saved in PPTPVBUF, a ring buffer of length 512 bytes.

TLM_0.2. DD2TM

The DDEIS data for each DDC consists of 12 channels of 16-bit accumulations. These are saved in a ring buffer, DD16BUF, which holds 128 DDC's, or half an MJF. DD2TM is initiated at the same time as PP2TM and compresses the last 64 DDC's data PSRL 16 to 10 into 15 bytes per DDC or 960 bytes, which are stored in the telemetry buffer DDTMBUF, of length 1920 bytes.

TLM_0.3. PP120BIN

Half of PP16BUF is merged from 256 to 120 bins by PP2TM. The 120 channels will be mapped from 256 accumulators as follows (Note that there is even symmetry, and the coding algorithm is very strange.)

| Degrees | Bins | Re-bin Ratio | Accumulator ID |
|---------|------|--------------------|----------------|
| 0- 20 | 0-27 | 1 to 1 or 28 to 28 | 0-54 even #'s |

| | | | | |
|---------|--------|--------------------|---------|----------|
| 20- 29 | 28-34 | 1 to 2 or 7 to 14 | 56-82 | even #'s |
| 29- 80 | 35-52 | 1 to 4 or 18 to 72 | 84-226 | even #'s |
| 80- 90 | 53-59 | 1 to 2 or 7 to 14 | 228-254 | even #'s |
| 90-100 | 60-66 | 1 to 2 or 7 to 14 | 255-229 | odd #'s |
| 100-151 | 67-84 | 1 to 4 or 18 to 72 | 227-85 | odd #'s |
| 151-160 | 85-91 | 1 to 2 or 7 to 14 | 83-57 | odd #'s |
| 160-180 | 92-119 | 1 to 1 or 28 to 28 | 55-1 | odd #'s |

| Total Bins | <u>120</u> | <u>256</u> |
|------------|------------|------------|
|------------|------------|------------|

TLM_0.4. CS8to5

ModeZero data are conveniently compressed and stacked by taking 4 16-bit data words, compressing them PSRL 16 to 10 bits each, and packing them into 5 bytes. Each DDEIS readout can be handled by repeating this subtask 3 times, and each PPA readout by repeating this subtask 30 times.

TLM_0.5. PSRL16to10

Pseudo-Root with Linear Segment compression of a 2 byte data word into a 10 bit word.

PSRL1610. Pseudo-Root with Linear Segment Compression Format

16bit to 10bit Psuedo-Root with Linear Segment compression. The bits of the original word are labelled q15 --> q0, with q15 being the high-order bit. (Say "aqqumulator.")

If the most significant bit is in this position

| Then the 10 bits of the compressed word are as follows | | | | | | | | | | with E/O | R/S |
|---|-----|-----|-----|-----|-----|-----|-----|-----|-----|----------|-----|
| q15 | q15 | q14 | q13 | q12 | q11 | q10 | q09 | q08 | 0 | 0 | |
| q14 | q14 | q13 | q12 | q11 | q10 | q09 | q08 | q07 | 1 | 0 | |
| q13 | 0 | q13 | q12 | q11 | q10 | q09 | q08 | q07 | 0 | 0 | |
| q12 | 0 | q12 | q11 | q10 | q09 | q08 | q07 | q06 | 1 | 0 | |
| q11 | 0 | 0 | q11 | q10 | q09 | q08 | q07 | q06 | 0 | 0 | |
| q10 | 0 | 0 | q10 | q09 | q08 | q07 | q06 | q05 | 1 | 0 | |
| q09 | 0 | 0 | 0 | q09 | q08 | q07 | q06 | q05 | 0 | 0 | |
| <q09 | q08 | q07 | q06 | q05 | q04 | q03 | q02 | q01 | q00 | 1 | |

S175_3.0. Science Status and Housekeeping Data for ModeThree
September 29, 1996

MODIFICATIONS

07-20-92 11:00 am r wf: Resynch interval referred to in sections .5.4.1. thru .5.4.3. was changed to a variable with default value of 63 MJF's on April 1, 1992.
10-29-93 r wf: Update from ModeZero to ModeTwo.
10-29-93 r wf: Update from ModeTwo to ModeThree.

S175_3.1.0. Flags and Status

S175_3.1.1. PPAOV1

There was an overflow upon replace-adding the 8 bit PPA RAM PP8_BUF into 16 bit PPA RAM PP16_BUF. Not needed if there are fewer than 256 replace-adds.

S175_3.1.2. PPAOV2

There was an overflow upon rebinning the PPA accumulators in task PP2TM.

S175_3.1.3. PPBSTAT

A four bit field corresponding to the magnetometer scale and special mode fields given to us by the magnetometer. The most recent value of this field is telemetered. This alerts us to changes in scale, which may be an error condition, and also gives us an idea of the S/N ratio of the magnetometer. This field must be associated with the data from its own PPC, and there must be 4 of them per MJF.

S175_3.2.0. Pulse Height Spectral Information

Not implemented in ModeZero, ModeOne, or ModeTwo

| | |
|-------------------------------------|---------------------------------------|
| HV deflection voltage monitor | 2 bytes + 2 bytes |
| CEM bias level monitor | Check with Jerry. I think he does it. |
| PHA input MUX | 4 bits |
| Duty accumulator number (1-6 or 12) | |
| Ion/Electron CEM | |
| PHA discrimination level | 8 bits |
| Deflection bias level | 1 byte |
| Reading of duty accum | 3 bytes + 3 bytes |
| Reading of PHA accum | 3 bytes + 3 bytes |

Summation:

| | |
|------------------|----------|
| Data | 12 bytes |
| Identification | 3 bytes |
| Voltage monitors | + 4 |

Total for 2 HEIS's

19 bytes

S175_3.3.0. Mode and Descriptor Information

There are 8 DDEIS and 4 PPA descriptors in the descriptor table. The entire table is telemetered, at the rate of one PPA and one DDEIS descriptor per MJF. That is, each MJF we get:

| | |
|-------------------------|----------|
| DDEIS descriptor | 13 bytes |
| DDEIS descriptor offset | 1 byte |
| PPA descriptor | 12 bytes |

The DDEIS descriptor offset is counted linearly from the start of the descriptor table. Since the DDEIS descriptors are 13 bytes long, and the table is 8 descriptors long, the offset values = N*13, where N=0-7, and N is the descriptor address used to determine the descriptor sequence (e.g.: address of next descriptor). The address of the PPA descriptor is derivable from that of the DDEIS, and is simply N/2.

| | |
|--------------------------|---------|
| DDEIS | |
| Scan Base Level | 1 byte |
| 0 <= Base <= 127 | |
| Scan Increment | 1 byte |
| Number of HV Steps | 1 byte |
| Per Scan (DDN's/DSC) | |
| Offset Base (+-Levels) | 1 byte |
| Offset Increment (+-) | 1 byte |
| Scans Per Offset Cycle | 1 byte |
| # Interrupts per | 2 bytes |
| Energy Step (BCI's/DDN) | |
| # Interrupts per | 2 bytes |
| Accumulation (BCI's/DDC) | |
| Address of Next | 1 byte |
| Scan Descriptor | |
| Address of Next | 1 byte |
| Cycle Descriptor | |
| Sensor Polarity | 1 byte |
| PPA | |
| Scan Base Level | 1 byte |
| 0 <= Base <= 127 | |
| Scan Increment | 1 byte |
| Number of HV Steps | 1 byte |
| Per Scan | |
| Offset Base (+-Levels) | 1 byte |
| Offset Increment (+-) | 1 byte |
| Scans Per Offset Cycle | 1 byte |
| # Interrupts per | 2 bytes |
| Energy Step (BCI's/DDN) | |
| # Interrupts per | 2 bytes |
| Accumulation (BCI's/DDC) | |

| | |
|---|----------|
| Address of Next Scan Descriptor | 1 byte |
| Address of Next Cycle Descriptor | 1 byte |
| Sensor Polarity (space holder) | 1 byte |
| - | |
| Values for control registers BCI, ET1, ET2, ACC, DSP | 10 bytes |

S175_3.4.0. Sampling Sequence States

Piggyback on PHA sequence. See PHA output.

Voltage monitors.

- PP CEM bias
- DD ion CEM bias
- DD electron CEM bias
- PP deflection bias, 128 levels
- DD deflection bias, +- 64 levels

Not implemented in ModeZero, ModeOne, or ModeTwo.

S175_3.4.1. PPA HV level

One byte included in the 4,3,4,3 part of the output buffer. Each accumulation is labeled by its HV level.

S175_3.5.0. Timing and Reference Marks

The spacecraft provides a universal time code consisting of 32 bits of data including: 15 bits of "Truncated Julian Day (TJD)" data, and 17 bits of "Seconds of Day". The most significant bit of the TJD is transmitted first, and the LSB = 1 second. This UTC is received by the TIM interrupt and stored.

The spacecraft also provides a Time Code Clock, which runs continuously at 1.000+/-0.004 kbps. This clock feeds the 16 bit Time Code Clock (TCC) register, which is reset by the Time Code Enable pulse, which occurs once for every UTC word. Thus, the TCC register counts milliseconds between UTC words.

Time is defined to a millisecond by reading the UTC code (4 bytes) and the TCC register (2 bytes), and putting them together for a 6 byte field, which we can call MSTIM. This is the straightforward way of providing a time mark.

S175_3.5.1. DDCYCTIM, 4 bytes

Each time a new DDEIS offset cycle begins, the spacecraft time is read, and written to memory with the present and previous descriptor numbers. These numbers are read out to telemetry once per MJF to create a timing reference in the scan

sequence. Since the 2 most significant bytes will be the same as for MJFTIM, 6 bytes are truncated to the least significant 4 bytes.

See TLMLB_2.FID for the byte assignments in telemetry.

Not implemented in ModeZero.

S175_3.5.2. DUNTIM, 4 bytes

Time read at the arrival of a DUN interrupt. Since the 2 most significant bytes will be the same as for MJFTIM, 6 bytes are truncated to the least significant 4 bytes.

S175_3.5.3. MJFTIM, 6 bytes

Time read at the arrival of a MJF pulse from the spacecraft (6 bytes).

S175_3.5.4. Synchronization Markers

S175_3.5.4.1. MRCD_NUM, 1 byte

Most recently commanded descriptor number. This identifies the most recently commanded DDEIS descriptor by its offset value. Every resynchronization interval, the program is reinitialized to this descriptor.

S175_3.5.4.2. PPMRCD_NUM, 1 byte

Most recently commanded descriptor number. This identifies the most recently commanded PPA descriptor by its offset value. Every 63 MJF's, the program is reinitialized to this descriptor.

S175_3.5.4.3. RESYNCH_MJF, 1 byte

The value of the low byte of the major frame counter, at which the next resynchronization occurs. Resynch occurs after this number of MJF's.

S175_3.5.4.4. MJF_CNT

The major frame counter maintained by the MJF ISR. The counter itself is one word, or 2 bytes, but only the least significant byte is telemetered, as this is the only one that matters modulo 8.

S175_3.6. Task Scheduler/Tables

A block of bytes to monitor the operation of the task scheduler.

S175_3.7. Memory Dump

A block of bytes to slowly go through memory and read it out.

*

TIMMTX_0.0. Timing Relationships Among Hydra Intervals

Generated by SuperCalc4 File \SC\TIMFID_0.CAL
To print this text, use 132 columns

9/ 5/91

TIMMTX_0.1. Nomenclature

BCI Basis Cycle Interrupt (programmable)
BFR Magnetometer data refresh cycle
BSP Magnetometer sample period
DDC DDEIS accumulation interval
DDN DDEIS energy step interval
DSC DDEIS energy scan period (programmable)
ET2 Experiment timing signal #2, generated internally
MJF Major Frame Period
MNF Minor Frame Period
PPC PPA accumulation interval, summed in scratch RAM over
some number of PPR cycles, and
read out to telemetry.
PPL The live accumulation portion of the PPR
PPR PPA RAM refresh interval (readout and reset the 8 bit
RAM on the PPA board.)
PSC PPA energy scan period (programmable)
SEC One NBS standard second
SPT Tick of spin phase reference clock (4096 per sun reference pulse)
SUN Sun reference pulse (=spin period)
TMT Tick of the 55652 hz telemetry clock

TIMMTX_0.2. Spacecraft Signals

| | # of THESE | in THAT | | | | | SPACECRAFT SIGNALS | | | | |
|-----|---------------|---------|---------|---------|---------|----------|--------------------|--|--|--|--|
| | | TMT | MNF | SEC | SUN | MJF | | | | | |
| TMT | 1 | 2048 | 55652 | 333912 | 512000 | | | | | | |
| MNF | .00049 | | 1 | 27.1738 | 163.043 | 250 | | | | | |
| SEC | .00002 | .036800 | | 1 | 6 | 9.200029 | | | | | |
| SUN | 3.0e-6 | .006133 | .166667 | | 1 | 1.533338 | | | | | |
| MJF | 2.0e-6 | .004 | .108695 | .652172 | | 1 | | | | | |

TIMMTX_0.3. Control Values

| # of | | in THAT | | CONTROL VALUES | | | | | | | | | | | | | | |
|-------|-----|---------|------|----------------|-----|------|------|------|-----|-----|------|-----|-------|-----|------|-----|-----|--|
| THESE | | | | BCI | | | DDC | | DDN | | MNF | | SEC | | SUN | | MJF | |
| | | | | ET2 | BSP | PPL | PPR | BFR | DDC | DDN | MNF | DSC | SEC | PPC | SUN | MJF | PSC | |
| TMT | 1 | 200 | 1000 | | | 1000 | 1000 | 1000 | | | 2048 | | 55652 | | | | TMT | |
| SPT | 1 | | | | | | | | | | | | | | 4096 | | SPT | |
| ET2 | | 1 | | | | 4 | | | | | | | | | | | ET2 | |
| BSP | | | 1 | | | | | | | | 4 | | | | | | BSP | |
| BCI | | | | 1 | | | | | 2 | 2 | | | | | | | BCI | |
| PPL | | | | | 1 | 1 | | | | | | | | | | | PPL | |
| PPR | | | | | | 1 | | | | | | | | | | | PPR | |
| BFR | | | | | | 1 | 1 | | | | | | | | | | BFR | |
| DDC | | | | | | | | 1 | | | | 16 | | | | | DDC | |
| DDN | | | | | | | | | 1 | | | | | | | | DDN | |
| MNF | | | | | | | | | | 1 | | | | | 250 | | MNF | |
| DSC | | | | | | | | | | | 1 | | | | | | DSC | |
| SEC | | | | | | | | | | | 1 | | 1 | 6 | | | SEC | |
| PPC | | | | | | | | | | | | | 1 | | 4 | 16 | PPC | |
| SUN | | | | | | | | | | | | | | 1 | | | SUN | |
| MJF | | | | | | | | | | | | | | 1 | | | MJF | |
| PSC | | | | | | | | | | | | | | | 1 | PSC | | |
| | TMT | SPT | ET2 | BSP | BCI | PPL | PPR | BFR | DDC | DDN | MNF | DSC | SEC | PPC | SUN | MJF | PSC | |

TIMMTX_0.4. Hydra and Spacecraft Signals

| # of | | in THAT | | HYDRA AND SPACECRAFT SIGNALS | | | | | | | | | | | | | | | |
|-------|-----|---------|-------|------------------------------|-------|-------|-------|-------|-------|-------|-------|--------|--------|---------|---------|--------|---------|----------|-----|
| THESE | | | | BCI | | | DDC | | DDN | | MNF | | SEC | | SUN | | MJF | | |
| | | | | ET2 | BSP | PPL | PPR | BFR | DDC | DDN | MNF | DSC | SEC | PPC | SUN | MJF | PSC | | |
| TMT | 1 | 81.52 | 200 | 512 | 1000 | 800 | 1000 | 1000 | 2000 | 2000 | 2048 | 32000 | 55652 | 128000 | 333912 | 512000 | 2048000 | TMT | |
| SPT | 1 | | 6.281 | 12.27 | | 12.27 | 12.27 | | | | | 682.67 | | | 4096 | | | SPT | |
| ET2 | | 1 | | | 4 | | | | | | | | | | | | ET2 | | |
| BSP | | | 1 | | | 1.953 | | | | | 4 | 108.70 | | | | 1000 | | BSP | |
| BCI | | | | 1 | | | | | 2 | 2 | | 32 | 55.652 | 128 | | | 512 | BCI | |
| PPL | | | | | | 1 | 1 | | | | 2.048 | | | 128 | | 512 | 2048 | PPL | |
| PPR | | | | | | | 1 | 1 | | | 2.048 | 55.652 | 128 | | | 512 | 2048 | PPR | |
| BFR | | | | | | | 1 | 1 | | | 2.048 | 55.652 | 128 | | | 512 | 2048 | BFR | |
| DDC | | | | | | | | | 1 | | | 16 | | 64 | | 256 | | DDC | |
| DDN | | | | | | | | | | 1 | | | | | | | DDN | | |
| MNF | | .0005 | | | | | | | | | 1 | 15.625 | 27.174 | | 163.043 | | 250 | MNF | |
| DSC | | | | | | | | | | | | 1 | | | | 16 | DSC | | |
| SEC | | 2e-5 | .0015 | | .0092 | .0180 | .0144 | .0180 | .0180 | .0359 | | .0368 | .57500 | 1 | 2.30001 | 6 | 9.20003 | 36.80012 | SEC |
| PPC | | | | | | | | | | | | | | 1 | | 4 | 16 | PPC | |
| SUN | | 3e-6 | | | | | | | | | .0061 | | .16667 | .383335 | | 1 | 1.53334 | | SUN |
| MJF | | 2e-6 | | | | | | | | | .004 | | .10870 | .25 | .652172 | | 1 | | MJF |
| PSC | | | | | | | | | | | | | | | | 1 | PSC | | |
| | TMT | SPT | ET2 | BSP | BCI | PPL | PPR | BFR | DDC | DDN | MNF | DSC | SEC | PPC | SUN | MJF | PSC | | |



| | | | | | | | | | | | | |
|----|----|----|----|----|----|----|----|----|----|-----|-----|-----|
| m0 | m1 | m2 | m3 | m4 | m5 | m6 | m7 | m8 | m9 | m10 | m11 | m12 |
| v | v0 | v1 | v2 | v3 | v4 | v5 | v6 | v7 | v8 | v9 | v10 | v11 |
| M | M | M0 | M1 | M2 | M3 | M4 | M5 | M6 | M7 | M8 | M9 | M10 |
| d | | d0 | | d1 | | d2 | | d3 | | d4 | | d5 |

D

PL

EX

RO

HP

TM

P Table of 256 PPC bins is finished replace-adding, and ready to rebin and compress. The alternate buffer starts repla
 P Previous table of 120 PPC bins is finished compressing and ready for TM (150 bytes 4 times per MJF).
 b Magnetometer sample (4 x 16 bits) received (BSP).
 m Magnetic field direction (15 bits) generated (BFR).
 v Overflow datum (1 bit) generated (PPR).
 M Magnetometer and Overflow data (16 bits) combined and ready for TM (2 bytes 512 times per MJF).
 d DDEIS accumulators read into buffer (14 X 16 bits)
 D DDEIS accumulator buffer (64 X 12 X 10 bits) compressed, transferred, and ready for TM (15 bytes 256 times per MJF).
 S Science status data (175 bytes 1 time per MJF)

The generation sequence can be written

$$S + 4*(P + 64*(2*M + D))$$

generating the following number of bits per MJF:

$$175 + 4*(150 + 64*(2*2 + 15)) = 5639$$

Combining notations,

$$S175 + 4*(P150 + 64*(2*M2 + D15))$$

which can also be written,

$$S175 + 4*(P150 + 64*(2*M2)) + 256*D15 = 175 + 4*406 + 3840$$

The telemetry frame will be staged in three sections or buffers, corresponding to data from the science status buffer, the PPA buffer, and the DDEIS buffer. There is also a fourth source, namely engineering housekeeping, but as this will be handled totally by UNH, we can ignore it.

PPA Data

The PPA data consists of 120 channels of 16 bit accumulations compressed 16 to 10 to 150 bytes, plus 128 sectors of 2 bytes each, where the 2 bytes consist of 1 overflow bit, 7 theta bits, and 8 phi bits.

†

TLMTITLE. Telemetry Format

Description of Telemetry Allocations

for

ModeThree Operation of the

Hydra Instrument on the Polar Satellite

September 29, 1996

TLMF.ALL 0. Description of Telemetry Allocation

Introduction

The Polar telemetry frame contains 250 minor frames (mf) numbered 1-250 each of which contains 256 bytes numbered 0-255. Hydra gets word 12 in mf's 26, 32, 38, etc., through 248 for a total of 38 bytes, which are to be used for engineering housekeeping only. Hydra gets word 17 in minor frames 1-139 which are collectively referred to as the "loose bytes". Additionally, Hydra gets words 20, 28, etc. for a total of 22 bytes in all minor frames. Thus the frame looks like:

| | Byte | 0 | 12 | 17 | 20 | 28 | ... | 255 |
|----------------|------|---|----|----|----|----|-----|-----|
| Minor Frame | | | | | | | | |
| 1 | | | | x | x | x | xxx | |
| . | | | | | | | | |
| 26 | | x | | x | x | x | xxx | |
| . | | | | | | | | |
| 32 | | x | | x | x | x | xxx | |
| . | | | | | | | | |
| 139 | | | | x | x | x | xxx | |
| 140 | | x | | | x | x | xxx | |
| . | | | | | | | | |
| 248 | | x | | | x | x | xxx | |
| 249 | | | | | x | x | xxx | |
| 250 | | | | | x | x | xxx | |

The submatrix of words used by Hydra looks like

The bytes have been allocated as follows:

| | |
|---|---|
| e | engineering housekeeping, assigned by UNH, 38 bytes |
| h | science housekeeping, assigned by UNH, 23 bytes |
| s | science housekeeping, assigned by UCSD, 138 bytes |
| x | science data, assigned by UCSD, 5478 bytes |

Note: The bytes assigned by UCSD = 138 + 5478 = 5616. The bytes assigned by UNH = 23 + 38 = 61.

UCSD Allocated Bytes

Note: In the information that follows, the data designation word refers to 16-bit words while the designation byte refers to 8-bit words.

This is a description of the usage of the 5616 bytes of telemetry (tlm) allocation that are filled by the TLMOTASK. The other 61 bytes (out of 5677) are filled by code associated with the ISR's for mode 0. TLMOTASK is called four times per major frame by the PPASCAN task. It executes just "after" the two data collection tasks (SCAN and PPASCAN) have gathered enough data to fill about one-quarter of the space available for tlm.

| n | 0 | 1 | 2 | 3 | n+1 | 0 | major frame # |
|----------------|---|---|---|---|-----|---|---------------|
| | * | * | * | * | | * | quarter # |
| execution for: | 0 | 1 | 2 | 3 | | 0 | * |

When TLMOTASK executes it will process 128 words of theta/phi data, 256 words of PPA data (re-binned to 120 words) and 768 words of DDEIS data. The PPA and DDEIS data will be compressed using a psuedo-root with linear segment 16 to 10 bit compression scheme (PSRL16-10). In the course of execution of an entire major frame TLMOTASK also places data into a 138 byte buffer which is the UCSD portion of the "loose bytes" buffer.

As mentioned before, TLMOTASK splits the tlm into two buffers. The first can be thought of as the Science Data (SD) buffer and the second as the Science Management (SM) buffer. The SD buffer is actually only 2739 bytes long and is filled twice per major frame. The SD buffer is further split into two pieces each of which corresponds to a quarter of the major frame. Each piece has the one of the two following forms

Quarters 0 and 2



Quarters 1 and 3



A = Theta / Phi data, 256 bytes = 128 words, uncompressed
B = PPA data, 150 bytes = 256 bytes re-binned to 120 words
compressed with PSRL16-10
C = DDEIS data, 960 bytes = 768 words, compressed with
PSRL16-10
D = 4 (quarters 0 and 2) or 3 (quarters 1 and 3) bytes of
science housekeeping data

The SM buffer is 138 bytes long. It is divided into 5 pieces, a so called Fixed section and 4 Quarter sections. Each of the Quarter sections contains identically formatted, though distinct, data while the Fixed part contains information that is only required once per major frame.

TLMF.ALC_0. Allocation of Hydra's Words in the Polar Telemetry Matrix

mf #211 dd
 mf #212 eh dd
 mf #213 dd
 mf #214 dd
 mf #215 dd
 mf #216 dd
 mf #217 dd
 mf #218 eh dd
 mf #219 dd
 mf #220 dd
 mf #221 dd
 mf #222 dd
 mf #223 dd
 mf #224 eh dd
 mf #225 dd
 mf #226 dd
 mf #227 dd
 mf #228 dd
 mf #229 dd
 mf #230 eh dd
 mf #231 dd
 mf #232 dd
 mf #233 dd
 mf #234 dd
 mf #235 dd
 mf #236 eh dd
 mf #237 dd
 mf #238 dd
 mf #239 dd
 mf #240 dd
 mf #241 dd
 mf #242 eh dd
 mf #243 dd
 mf #244 dd
 mf #245 dd
 mf #246 dd
 mf #247 dd
 mf #248 eh dd
 mf #249 dd
 mf #250 dd s3 s3 s3

The bytes have been allocated as follows:

| | |
|----|---|
| eh | engineering housekeeping, assigned by UNH, 38 bytes |
| nh | science housekeeping, assigned by UNH, 23 bytes |
| sh | science housekeeping, also known as the "loose bytes" buffer, assigned by UCSD, 138 bytes |
| tp | theta/phi science data, assigned by UCSD, 1024 bytes |
| pp | ppa science data, assigned by UCSD, 600 bytes |
| dd | ddeis science data, assigned by UCSD, 3840 bytes |
| sn | n=0-3, science housekeeping associated with each quarter of the science data buffer, assigned by UCSD, 14 bytes |

TLMF.MFOFST_0. Minor Frame Offset List

The following is a cheat sheet to help programmers locate bytes within the Hydra telemetry display.

minor

| frame # | dec | hex | |
|---------|------------------------|------|--------------|
| mf # 1 | starting offset = 0 | 0000 | 17 20-198 |
| mf # 2 | starting offset = 23 | 0017 | 17 20-198 |
| mf # 3 | starting offset = 46 | 002E | 17 20-198 |
| mf # 4 | starting offset = 69 | 0045 | 17 20-198 |
| mf # 5 | starting offset = 92 | 005C | 17 20-198 |
| mf # 6 | starting offset = 115 | 0073 | 17 20-198 |
| mf # 7 | starting offset = 138 | 008A | 17 20-198 |
| mf # 8 | starting offset = 161 | 00A1 | 17 20-198 |
| mf # 9 | starting offset = 184 | 00B8 | 17 20-198 |
| mf # 10 | starting offset = 207 | 00CF | 17 20-198 |
| mf # 11 | starting offset = 230 | 00E6 | 17 20-198 |
| mf # 12 | starting offset = 253 | 00FD | 17 20-198 |
| mf # 13 | starting offset = 276 | 0114 | 17 20-198 |
| mf # 14 | starting offset = 299 | 012B | 17 20-198 |
| mf # 15 | starting offset = 322 | 0142 | 17 20-198 |
| mf # 16 | starting offset = 345 | 0159 | 17 20-198 |
| mf # 17 | starting offset = 368 | 0170 | 17 20-198 |
| mf # 18 | starting offset = 391 | 0187 | 17 20-198 |
| mf # 19 | starting offset = 414 | 019E | 17 20-198 |
| mf # 20 | starting offset = 437 | 01B5 | 17 20-198 |
| mf # 21 | starting offset = 460 | 01CC | 17 20-198 |
| mf # 22 | starting offset = 483 | 01E3 | 17 20-198 |
| mf # 23 | starting offset = 506 | 01FA | 17 20-198 |
| mf # 24 | starting offset = 529 | 0211 | 17 20-198 |
| mf # 25 | starting offset = 552 | 0228 | 17 20-198 |
| mf # 26 | starting offset = 575 | 023F | 12 17 20-198 |
| mf # 27 | starting offset = 599 | 0257 | 17 20-198 |
| mf # 28 | starting offset = 622 | 026E | 17 20-198 |
| mf # 29 | starting offset = 645 | 0285 | 17 20-198 |
| mf # 30 | starting offset = 668 | 029C | 17 20-198 |
| mf # 31 | starting offset = 691 | 02B3 | 17 20-198 |
| mf # 32 | starting offset = 714 | 02CA | 12 17 20-198 |
| mf # 33 | starting offset = 738 | 02E2 | 17 20-198 |
| mf # 34 | starting offset = 761 | 02F9 | 17 20-198 |
| mf # 35 | starting offset = 784 | 0310 | 17 20-198 |
| mf # 36 | starting offset = 807 | 0327 | 17 20-198 |
| mf # 37 | starting offset = 830 | 033E | 17 20-198 |
| mf # 38 | starting offset = 853 | 0355 | 12 17 20-198 |
| mf # 39 | starting offset = 877 | 036D | 17 20-198 |
| mf # 40 | starting offset = 900 | 0384 | 17 20-198 |
| mf # 41 | starting offset = 923 | 039B | 17 20-198 |
| mf # 42 | starting offset = 946 | 03B2 | 17 20-198 |
| mf # 43 | starting offset = 969 | 03C9 | 17 20-198 |
| mf # 44 | starting offset = 992 | 03E0 | 12 17 20-198 |
| mf # 45 | starting offset = 1016 | 03F8 | 17 20-198 |
| mf # 46 | starting offset = 1039 | 040F | 17 20-198 |

| | | | |
|---------|------------------------|------|--------------|
| mf # 47 | starting offset = 1062 | 0426 | 17 20-198 |
| mf # 48 | starting offset = 1085 | 043D | 17 20-198 |
| mf # 49 | starting offset = 1108 | 0454 | 17 20-198 |
| mf # 50 | starting offset = 1131 | 046B | 12 17 20-198 |
| mf # 51 | starting offset = 1155 | 0483 | 17 20-198 |
| mf # 52 | starting offset = 1178 | 049A | 17 20-198 |
| mf # 53 | starting offset = 1201 | 04B1 | 17 20-198 |
| mf # 54 | starting offset = 1224 | 04C8 | 17 20-198 |
| mf # 55 | starting offset = 1247 | 04DF | 17 20-198 |
| mf # 56 | starting offset = 1270 | 04F6 | 12 17 20-198 |
| mf # 57 | starting offset = 1294 | 050E | 17 20-198 |
| mf # 58 | starting offset = 1317 | 0525 | 17 20-198 |
| mf # 59 | starting offset = 1340 | 053C | 17 20-198 |
| mf # 60 | starting offset = 1363 | 0553 | 17 20-198 |
| mf # 61 | starting offset = 1386 | 056A | 17 20-198 |
| mf # 62 | starting offset = 1409 | 0581 | 12 17 20-198 |
| mf # 63 | starting offset = 1433 | 0599 | 17 20-198 |
| mf # 64 | starting offset = 1456 | 05B0 | 17 20-198 |
| mf # 65 | starting offset = 1479 | 05C7 | 17 20-198 |
| mf # 66 | starting offset = 1502 | 05DE | 17 20-198 |
| mf # 67 | starting offset = 1525 | 05F5 | 17 20-198 |
| mf # 68 | starting offset = 1548 | 060C | 12 17 20-198 |
| mf # 69 | starting offset = 1572 | 0624 | 17 20-198 |
| mf # 70 | starting offset = 1595 | 063B | 17 20-198 |
| mf # 71 | starting offset = 1618 | 0652 | 17 20-198 |
| mf # 72 | starting offset = 1641 | 0669 | 17 20-198 |
| mf # 73 | starting offset = 1664 | 0680 | 17 20-198 |
| mf # 74 | starting offset = 1687 | 0697 | 12 17 20-198 |
| mf # 75 | starting offset = 1711 | 06AF | 17 20-198 |
| mf # 76 | starting offset = 1734 | 06C6 | 17 20-198 |
| mf # 77 | starting offset = 1757 | 06DD | 17 20-198 |
| mf # 78 | starting offset = 1780 | 06F4 | 17 20-198 |
| mf # 79 | starting offset = 1803 | 070B | 17 20-198 |
| mf # 80 | starting offset = 1826 | 0722 | 12 17 20-198 |
| mf # 81 | starting offset = 1850 | 073A | 17 20-198 |
| mf # 82 | starting offset = 1873 | 0751 | 17 20-198 |
| mf # 83 | starting offset = 1896 | 0768 | 17 20-198 |
| mf # 84 | starting offset = 1919 | 077F | 17 20-198 |
| mf # 85 | starting offset = 1942 | 0796 | 17 20-198 |
| mf # 86 | starting offset = 1965 | 07AD | 12 17 20-198 |
| mf # 87 | starting offset = 1989 | 07C5 | 17 20-198 |
| mf # 88 | starting offset = 2012 | 07DC | 17 20-198 |
| mf # 89 | starting offset = 2035 | 07F3 | 17 20-198 |
| mf # 90 | starting offset = 2058 | 080A | 17 20-198 |
| mf # 91 | starting offset = 2081 | 0821 | 17 20-198 |
| mf # 92 | starting offset = 2104 | 0838 | 12 17 20-198 |
| mf # 93 | starting offset = 2128 | 0850 | 17 20-198 |
| mf # 94 | starting offset = 2151 | 0867 | 17 20-198 |
| mf # 95 | starting offset = 2174 | 087E | 17 20-198 |
| mf # 96 | starting offset = 2197 | 0895 | 17 20-198 |
| mf # 97 | starting offset = 2220 | 08AC | 17 20-198 |
| mf # 98 | starting offset = 2243 | 08C3 | 12 17 20-198 |
| mf # 99 | starting offset = 2267 | 08DB | 17 20-198 |
| mf #100 | starting offset = 2290 | 08F2 | 17 20-198 |

| | | | | |
|---------|------------------------|------|----|-----------|
| mf #101 | starting offset = 2313 | 0909 | 17 | 20-198 |
| mf #102 | starting offset = 2336 | 0920 | 17 | 20-198 |
| mf #103 | starting offset = 2359 | 0937 | 17 | 20-198 |
| mf #104 | starting offset = 2382 | 094E | 12 | 17 20-198 |
| mf #105 | starting offset = 2406 | 0966 | 17 | 20-198 |
| mf #106 | starting offset = 2429 | 097D | 17 | 20-198 |
| mf #107 | starting offset = 2452 | 0994 | 17 | 20-198 |
| mf #108 | starting offset = 2475 | 09AB | 17 | 20-198 |
| mf #109 | starting offset = 2498 | 09C2 | 17 | 20-198 |
| mf #110 | starting offset = 2521 | 09D9 | 12 | 17 20-198 |
| mf #111 | starting offset = 2545 | 09F1 | 17 | 20-198 |
| mf #112 | starting offset = 2568 | 0A08 | 17 | 20-198 |
| mf #113 | starting offset = 2591 | 0A1F | 17 | 20-198 |
| mf #114 | starting offset = 2614 | 0A36 | 17 | 20-198 |
| mf #115 | starting offset = 2637 | 0A4D | 17 | 20-198 |
| mf #116 | starting offset = 2660 | 0A64 | 12 | 17 20-198 |
| mf #117 | starting offset = 2684 | 0A7C | 17 | 20-198 |
| mf #118 | starting offset = 2707 | 0A93 | 17 | 20-198 |
| mf #119 | starting offset = 2730 | 0AAA | 17 | 20-198 |
| mf #120 | starting offset = 2753 | 0AC1 | 17 | 20-198 |
| mf #121 | starting offset = 2776 | 0AD8 | 17 | 20-198 |
| mf #122 | starting offset = 2799 | 0AEF | 12 | 17 20-198 |
| mf #123 | starting offset = 2823 | 0B07 | 17 | 20-198 |
| mf #124 | starting offset = 2846 | 0B1E | 17 | 20-198 |
| mf #125 | starting offset = 2869 | 0B35 | 17 | 20-198 |
| mf #126 | starting offset = 2892 | 0B4C | 17 | 20-198 |
| mf #127 | starting offset = 2915 | 0B63 | 17 | 20-198 |
| mf #128 | starting offset = 2938 | 0B7A | 12 | 17 20-198 |
| mf #129 | starting offset = 2962 | 0B92 | 17 | 20-198 |
| mf #130 | starting offset = 2985 | 0BA9 | 17 | 20-198 |
| mf #131 | starting offset = 3008 | 0BC0 | 17 | 20-198 |
| mf #132 | starting offset = 3031 | 0BD7 | 17 | 20-198 |
| mf #133 | starting offset = 3054 | 0BEE | 17 | 20-198 |
| mf #134 | starting offset = 3077 | 0C05 | 12 | 17 20-198 |
| mf #135 | starting offset = 3101 | 0C1D | 17 | 20-198 |
| mf #136 | starting offset = 3124 | 0C34 | 17 | 20-198 |
| mf #137 | starting offset = 3147 | 0C4B | 17 | 20-198 |
| mf #138 | starting offset = 3170 | 0C62 | 17 | 20-198 |
| mf #139 | starting offset = 3193 | 0C79 | 17 | 20-198 |
| mf #140 | starting offset = 3216 | 0C90 | 12 | 20-198 |
| mf #141 | starting offset = 3239 | 0CA7 | | 20-198 |
| mf #142 | starting offset = 3261 | 0CBD | | 20-198 |
| mf #143 | starting offset = 3283 | 0CD3 | | 20-198 |
| mf #144 | starting offset = 3305 | 0CE9 | | 20-198 |
| mf #145 | starting offset = 3327 | 0CFF | | 20-198 |
| mf #146 | starting offset = 3349 | 0D15 | 12 | 20-198 |
| mf #147 | starting offset = 3372 | 0D2C | | 20-198 |
| mf #148 | starting offset = 3394 | 0D42 | | 20-198 |
| mf #149 | starting offset = 3416 | 0D58 | | 20-198 |
| mf #150 | starting offset = 3438 | 0D6E | | 20-198 |
| mf #151 | starting offset = 3460 | 0D84 | | 20-198 |
| mf #152 | starting offset = 3482 | 0D9A | 12 | 20-198 |
| mf #153 | starting offset = 3505 | 0DB1 | | 20-198 |
| mf #154 | starting offset = 3527 | 0DC7 | | 20-198 |

| | | | |
|---------|------------------------|------|-----------|
| mf #155 | starting offset = 3549 | 0DDD | 20-198 |
| mf #156 | starting offset = 3571 | 0DF3 | 20-198 |
| mf #157 | starting offset = 3593 | 0E09 | 20-198 |
| mf #158 | starting offset = 3615 | 0E1F | 12 20-198 |
| mf #159 | starting offset = 3638 | 0E36 | 20-198 |
| mf #160 | starting offset = 3660 | 0E4C | 20-198 |
| mf #161 | starting offset = 3682 | 0E62 | 20-198 |
| mf #162 | starting offset = 3704 | 0E78 | 20-198 |
| mf #163 | starting offset = 3726 | 0E8E | 20-198 |
| mf #164 | starting offset = 3748 | 0EA4 | 12 20-198 |
| mf #165 | starting offset = 3771 | 0EBB | 20-198 |
| mf #166 | starting offset = 3793 | 0ED1 | 20-198 |
| mf #167 | starting offset = 3815 | 0EE7 | 20-198 |
| mf #168 | starting offset = 3837 | 0EFD | 20-198 |
| mf #169 | starting offset = 3859 | 0F13 | 20-198 |
| mf #170 | starting offset = 3881 | 0F29 | 12 20-198 |
| mf #171 | starting offset = 3904 | 0F40 | 20-198 |
| mf #172 | starting offset = 3926 | 0F56 | 20-198 |
| mf #173 | starting offset = 3948 | 0F6C | 20-198 |
| mf #174 | starting offset = 3970 | 0F82 | 20-198 |
| mf #175 | starting offset = 3992 | 0F98 | 20-198 |
| mf #176 | starting offset = 4014 | 0FAE | 12 20-198 |
| mf #177 | starting offset = 4037 | 0FC5 | 20-198 |
| mf #178 | starting offset = 4059 | 0FDB | 20-198 |
| mf #179 | starting offset = 4081 | 0FF1 | 20-198 |
| mf #180 | starting offset = 4103 | 1007 | 20-198 |
| mf #181 | starting offset = 4125 | 101D | 20-198 |
| mf #182 | starting offset = 4147 | 1033 | 12 20-198 |
| mf #183 | starting offset = 4170 | 104A | 20-198 |
| mf #184 | starting offset = 4192 | 1060 | 20-198 |
| mf #185 | starting offset = 4214 | 1076 | 20-198 |
| mf #186 | starting offset = 4236 | 108C | 20-198 |
| mf #187 | starting offset = 4258 | 10A2 | 20-198 |
| mf #188 | starting offset = 4280 | 10B8 | 12 20-198 |
| mf #189 | starting offset = 4303 | 10CF | 20-198 |
| mf #190 | starting offset = 4325 | 10E5 | 20-198 |
| mf #191 | starting offset = 4347 | 10FB | 20-198 |
| mf #192 | starting offset = 4369 | 1111 | 20-198 |
| mf #193 | starting offset = 4391 | 1127 | 20-198 |
| mf #194 | starting offset = 4413 | 113D | 12 20-198 |
| mf #195 | starting offset = 4436 | 1154 | 20-198 |
| mf #196 | starting offset = 4458 | 116A | 20-198 |
| mf #197 | starting offset = 4480 | 1180 | 20-198 |
| mf #198 | starting offset = 4502 | 1196 | 20-198 |
| mf #199 | starting offset = 4524 | 11AC | 20-198 |
| mf #200 | starting offset = 4546 | 11C2 | 12 20-198 |
| mf #201 | starting offset = 4569 | 11D9 | 20-198 |
| mf #202 | starting offset = 4591 | 11EF | 20-198 |
| mf #203 | starting offset = 4613 | 1205 | 20-198 |
| mf #204 | starting offset = 4635 | 121B | 20-198 |
| mf #205 | starting offset = 4657 | 1231 | 20-198 |
| mf #206 | starting offset = 4679 | 1247 | 12 20-198 |
| mf #207 | starting offset = 4702 | 125E | 20-198 |
| mf #208 | starting offset = 4724 | 1274 | 20-198 |

| | | | |
|---------|------------------------|------|-----------|
| mf #209 | starting offset = 4746 | 128A | 20-198 |
| mf #210 | starting offset = 4768 | 12A0 | 20-198 |
| mf #211 | starting offset = 4790 | 12B6 | 20-198 |
| mf #212 | starting offset = 4812 | 12CC | 12 20-198 |
| mf #213 | starting offset = 4835 | 12E3 | 20-198 |
| mf #214 | starting offset = 4857 | 12F9 | 20-198 |
| mf #215 | starting offset = 4879 | 130F | 20-198 |
| mf #216 | starting offset = 4901 | 1325 | 20-198 |
| mf #217 | starting offset = 4923 | 133B | 20-198 |
| mf #218 | starting offset = 4945 | 1351 | 12 20-198 |
| mf #219 | starting offset = 4968 | 1368 | 20-198 |
| mf #220 | starting offset = 4990 | 137E | 20-198 |
| mf #221 | starting offset = 5012 | 1394 | 20-198 |
| mf #222 | starting offset = 5034 | 13AA | 20-198 |
| mf #223 | starting offset = 5056 | 13C0 | 20-198 |
| mf #224 | starting offset = 5078 | 13D6 | 12 20-198 |
| mf #225 | starting offset = 5101 | 13ED | 20-198 |
| mf #226 | starting offset = 5123 | 1403 | 20-198 |
| mf #227 | starting offset = 5145 | 1419 | 20-198 |
| mf #228 | starting offset = 5167 | 142F | 20-198 |
| mf #229 | starting offset = 5189 | 1445 | 20-198 |
| mf #230 | starting offset = 5211 | 145B | 12 20-198 |
| mf #231 | starting offset = 5234 | 1472 | 20-198 |
| mf #232 | starting offset = 5256 | 1488 | 20-198 |
| mf #233 | starting offset = 5278 | 149E | 20-198 |
| mf #234 | starting offset = 5300 | 14B4 | 20-198 |
| mf #235 | starting offset = 5322 | 14CA | 20-198 |
| mf #236 | starting offset = 5344 | 14E0 | 12 20-198 |
| mf #237 | starting offset = 5367 | 14F7 | 20-198 |
| mf #238 | starting offset = 5389 | 150D | 20-198 |
| mf #239 | starting offset = 5411 | 1523 | 20-198 |
| mf #240 | starting offset = 5433 | 1539 | 20-198 |
| mf #241 | starting offset = 5455 | 154F | 20-198 |
| mf #242 | starting offset = 5477 | 1565 | 12 20-198 |
| mf #243 | starting offset = 5500 | 157C | 20-198 |
| mf #244 | starting offset = 5522 | 1592 | 20-198 |
| mf #245 | starting offset = 5544 | 15A8 | 20-198 |
| mf #246 | starting offset = 5566 | 15BE | 20-198 |
| mf #247 | starting offset = 5588 | 15D4 | 20-198 |
| mf #248 | starting offset = 5610 | 15EA | 12 20-198 |
| mf #249 | starting offset = 5633 | 1601 | 20-198 |
| mf #250 | starting offset = 5655 | 1617 | 20-198 |

TLMF.TLMDD_0. The DDEIS Data Buffer

This is a description of a single DDEIS data buffer from the Hydra Mode 0 telemetry. There are 4 of these buffers per major frame. There are 960 bytes per buffer, representing 768 16-bit words of DDEIS data.

Each set of 5 bytes represents 4 compressed 16-Bit words. Each word uses 10 bits, derived from the 16-10 Psuedo-Root with Linear Segment compression algorithm. The following diagram shows which bits of each byte to use for each word.

| Byte# | 4 | 3 | 2 | 1 | 0 |
|-------|----------|----------|----------|----------|----------|
| | 33333333 | 33222222 | 22221111 | 11111100 | 00000000 |

Each set of 5 bytes is referred to here as a "compression set" since for the purposes of deconstruction the 5 bytes are turned into 4 words.

Offset

| | | |
|----|-------|---------------------------------|
| 0 | Words | 0-3, Compression Set 0, Byte 0 |
| 1 | Words | 0-3, Compression Set 0, Byte 1 |
| 2 | Words | 0-3, Compression Set 0, Byte 2 |
| 3 | Words | 0-3, Compression Set 0, Byte 3 |
| 4 | Words | 0-3, Compression Set 0, Byte 4 |
| 5 | Words | 4-7, Compression Set 1, Byte 0 |
| 6 | Words | 4-7, Compression Set 1, Byte 1 |
| 7 | Words | 4-7, Compression Set 1, Byte 2 |
| 8 | Words | 4-7, Compression Set 1, Byte 3 |
| 9 | Words | 4-7, Compression Set 1, Byte 4 |
| 10 | Words | 8-11, Compression Set 2, Byte 0 |
| 11 | Words | 8-11, Compression Set 2, Byte 1 |
| 12 | Words | 8-11, Compression Set 2, Byte 2 |
| 13 | Words | 8-11, Compression Set 2, Byte 3 |
| 14 | Words | 8-11, Compression Set 2, Byte 4 |

.

.

.

F Words 4*N to 3+4*N, Compression Set N, Byte F-5*N

where F = Offset, (0 <= F <= 959)
N = INT(F/5), (0 <= N <= 191)

.

.

.

| | |
|-----|--|
| 945 | Words 756-759, Compression Set 189, Byte 0 |
| 946 | Words 756-759, Compression Set 189, Byte 1 |
| 947 | Words 756-759, Compression Set 189, Byte 2 |
| 948 | Words 756-759, Compression Set 189, Byte 3 |
| 949 | Words 756-759, Compression Set 189, Byte 4 |
| 950 | Words 760-763, Compression Set 190, Byte 0 |
| 951 | Words 760-763, Compression Set 190, Byte 1 |
| 952 | Words 760-763, Compression Set 190, Byte 2 |
| 953 | Words 760-763, Compression Set 190, Byte 3 |
| 954 | Words 760-763, Compression Set 190, Byte 4 |
| 955 | Words 764-767, Compression Set 191, Byte 0 |

956 Words 764-767, Compression Set 191, Byte 1
957 Words 764-767, Compression Set 191, Byte 2
958 Words 764-767, Compression Set 191, Byte 3
959 Words 764-767, Compression Set 191, Byte 4

TLMF.TLMPP_0. The PPA Data Buffer

This is a description of a single PPA data buffer from the Hydra Mode 0 telemetry. There are 4 of these buffers per major frame. There are 150 bytes per buffer, representing 120 16-bit words of PPA data. These 120 words are the 120 Bins of PPA data representing 0-180 degrees produced by the TLM0 Task.

- Each set of 5 bytes represents 4 compressed 16-Bit words. Each word uses 10 bits, derived from the 16-10 Psuedo-Root with Linear Segment compression algorithm. The following diagram shows which bits of each byte to use for each word.

| Byte# | 4 | 3 | 2 | 1 | 0 |
|-------|----------|----------|----------|----------|----------|
| | 33333333 | 33222222 | 22221111 | 11111100 | 00000000 |

Each set of 5 bytes is referred to here as a "compression set" since for the purposes of deconstruction the 5 bytes are turned into 4 words.

Offset

| | | | |
|----|------|-----------------------|-----------|
| 0 | Bins | 0-3, Compression Set | 0, Byte 0 |
| 1 | Bins | 0-3, Compression Set | 0, Byte 1 |
| 2 | Bins | 0-3, Compression Set | 0, Byte 2 |
| 3 | Bins | 0-3, Compression Set | 0, Byte 3 |
| 4 | Bins | 0-3, Compression Set | 0, Byte 4 |
| 5 | Bins | 4-7, Compression Set | 1, Byte 0 |
| 6 | Bins | 4-7, Compression Set | 1, Byte 1 |
| 7 | Bins | 4-7, Compression Set | 1, Byte 2 |
| 8 | Bins | 4-7, Compression Set | 1, Byte 3 |
| 9 | Bins | 4-7, Compression Set | 1, Byte 4 |
| 10 | Bins | 8-11, Compression Set | 2, Byte 0 |
| 11 | Bins | 8-11, Compression Set | 2, Byte 1 |
| 12 | Bins | 8-11, Compression Set | 2, Byte 2 |
| 13 | Bins | 8-11, Compression Set | 2, Byte 3 |
| 14 | Bins | 8-11, Compression Set | 2, Byte 4 |

F Bins 4*N to 3+4*N, Compression Set N, Byte F-5*N
where F = Offset, (0 <= F <= 149)
 N = INT(F/5), (0 <= N <= 29)

| | |
|-----|--|
| 135 | Bins 108-111, Compression Set 27, Byte 0 |
| 136 | Bins 108-111, Compression Set 27, Byte 1 |
| 137 | Bins 108-111, Compression Set 27, Byte 2 |
| 138 | Bins 108-111, Compression Set 27, Byte 3 |
| 139 | Bins 108-111, Compression Set 27, Byte 4 |
| 140 | Bins 112-115, Compression Set 28, Byte 0 |
| 141 | Bins 112-115, Compression Set 28, Byte 1 |
| 142 | Bins 112-115, Compression Set 28, Byte 2 |
| 143 | Bins 112-115, Compression Set 28, Byte 3 |
| 144 | Bins 112-115, Compression Set 28, Byte 4 |

145 Bins 116-119, Compression Set 29, Byte 0
146 Bins 116-119, Compression Set 29, Byte 1
147 Bins 116-119, Compression Set 29, Byte 2
148 Bins 116-119, Compression Set 29, Byte 3
149 Bins 116-119, Compression Set 29, Byte 4

TLMF.TLMTP_0. The Theta-Phi Buffer

This is a description of a single theta/phi buffer from the Hydra Mode 0 telemetry. There are 4 of these buffers per major frame, with 128 16-bit words per buffer.

| Offset | Description |
|--------|-------------------------------|
| 0 | Theta/Phi word# 0 LSB |
| 1 | Theta/Phi word# 0 MSB |
| 2 | Theta/Phi word# 1 LSB |
| 3 | Theta/Phi word# 1 MSB |
| 4 | Theta/Phi word# 2 LSB |
| 5 | Theta/Phi word# 2 MSB |
| . | . |
| . | . |
| F | Theta/Phi word# N LSB |
| F | Theta/Phi word# N MSB |
| where | F = Offset, (0 <= F <= 255) |
| | N = INT(F/2), (0 <= N <= 127) |
| . | . |
| . | . |
| 250 | Theta/Phi word#125 LSB |
| 251 | Theta/Phi word#125 MSB |
| 252 | Theta/Phi word#126 LSB |
| 253 | Theta/Phi word#126 MSB |
| 254 | Theta/Phi word#127 LSB |
| 255 | Theta/Phi word#127 MSB |

TLMF.TLMSN 2. Quarterly Science Housekeeping Bytes

This is a description of the the Science Housekeeping bytes allocated by UCSD that are associated with each quarter of the science data buffer. They are designated sn in the master telemetry list.

| Name | Byte# | Description |
|------|-------|--|
| s0 | 0 | Error Flags, Scale Bits for this quarter |
| s0 | 1 | HV value of PPA data in this quarter |
| s0 | 2 | Not Used |
| s0 | 3 | Not Used |
| s1 | 0 | Error Flags, Scale Bits for this quarter |
| s1 | 1 | HV value of PPA data in this quarter |
| s1 | 2 | Not Used |
| s2 | 0 | Error Flags, Scale Bits for this quarter |
| s2 | 1 | HV value of PPA data in this quarter |
| s2 | 2 | Not Used |
| s2 | 3 | Not Used |
| s3 | 0 | Error Flags, Scale Bits for this quarter |
| s3 | 1 | HV value of PPA data in this quarter |
| s3 | 2 | Not Used |

Modes 0-1:

Byte 0 bits 0-3 magnetometer scale
bit 4 PPAOV2

Mode 2:

| | | |
|--------|----------|--|
| Byte 0 | bits 0-3 | magnetometer scale |
| | bit 4 | PPAOV2 |
| | bit 5 | Flag to indicate an external command occurred for a new DDEIS descriptor |
| | bit 6 | Flag to indicate an external command occurred for a new PPA descriptor |

TLMF.TLMLB_3. Science Housekeeping Loose Bytes

This is a description of the the Science Housekeeping bytes allocated by UCSD. They are also called the "loose bytes" telemetry, but UCSD does not use the first of the true loose bytes (those bytes occurring at word 17 in the telemetry list) as UNH has a use for it. These offsets are therefore relative to the UCSD buffer only.

MODIFICATIONS:

12-02-91 1:14:50 pm rdb: added ddeis hv dump and re-arranged everything else.
12-16-91 2:20:56 pm rdb: added 2 byte mode number at offset 136
4-01-92 1:34:52 pm rdb: changed name of init_mjf_mod8 to synch_mjf to correspond to changes made in code.
7-20-92 rwf: added explanatory footnotes 5-7. Clarified note 2 and items 80-83.
7-21-93 rdb:
10-20-93 rdb and rwf: Change to ModeTwo assignments
10-21-94 rdb and rwf: Change to ModeThree assignments
08-21-96 rdb and rwf: Correct footnote 1
09-27-96 rdb and rwf: Add item 66, pha match count

| | Offset | Description |
|----|--------|--|
| * | 0 | DDEIS High Voltage Setting #j+0 |
| | 1 | DDEIS High Voltage Setting #j+1 |
| | 2 | DDEIS High Voltage Setting #j+2 |
| | 3 | DDEIS High Voltage Setting #j+3 |
| | 4 | DDEIS High Voltage Setting #j+4 |
| | 5 | DDEIS High Voltage Setting #j+5 |
| | 6 | DDEIS High Voltage Setting #j+6 |
| | 7 | DDEIS High Voltage Setting #j+7 |
| | 8 | DDEIS HV table index of last electron peak |
| | 9 | DDEIS HV table index of last ion peak |
| | 10 | DDEIS HV control byte of last electron peak |
| | 11 | DDEIS HV control byte of last ion peak |
| | 12 | Side 2 PHA accumulator counts from previous MJF, byte 0 |
| | 13 | Side 2 PHA accumulator counts from previous MJF, byte 1 |
| | 14 | Side 2 PHA accumulator counts from previous MJF, byte 2 |
| | 15 | PHA HV control byte |
| *5 | 16 | LSB of BCI Count at Start of PPA Accum == pp_bcicnt |
| | 17 | DDEIS High Voltage Setting #j+8 |
| | 18 | DDEIS High Voltage Setting #j+9 |
| | 19 | DDEIS High Voltage Setting #j+10 |
| | 20 | DDEIS High Voltage Setting #j+11 |
| | 21 | DDEIS High Voltage Setting #j+12 |
| | 22 | DDEIS High Voltage Setting #j+13 |
| | 23 | DDEIS High Voltage Setting #j+14 |
| | 24 | DDEIS High Voltage Setting #j+15 |
| | 25 | DDEIS HV table index of last electron peak |
| | 26 | DDEIS HV table index of last ion peak |
| | 27 | DDEIS HV control byte of last electron peak |
| | 28 | DDEIS HV control byte of last ion peak |
| | 29 | Side 1 duty accumulator counts from previous MJF, byte 0 |
| | 30 | Side 1 duty accumulator counts from previous MJF, byte 1 |
| | 31 | Side 1 duty accumulator counts from previous MJF, byte 2 |

*5 32 PHA discriminator setting
33 LSB of BCI Count at Start of PPA Accum == pp_bcicnt
34 DDEIS High Voltage Setting #j+16
35 DDEIS High Voltage Setting #j+17
36 DDEIS High Voltage Setting #j+18
37 DDEIS High Voltage Setting #j+19
38 DDEIS High Voltage Setting #j+20
39 DDEIS High Voltage Setting #j+21
40 DDEIS High Voltage Setting #j+22
41 DDEIS High Voltage Setting #j+23
42 DDEIS HV table index of last electron peak
43 DDEIS HV table index of last ion peak
44 DDEIS HV control byte of last electron peak
45 DDEIS HV control byte of last ion peak
46 Side 2 duty accumulator counts from previous MJF, byte 0
47 Side 2 duty accumulator counts from previous MJF, byte 1
48 Side 2 duty accumulator counts from previous MJF, byte 2
49 PHA CEM MUX or-byte for current MJF
*5 50 LSB of BCI Count at Start of PPA Accum == pp_bcicnt
51 DDEIS High Voltage Setting #j+24
52 DDEIS High Voltage Setting #j+25
53 DDEIS High Voltage Setting #j+26
54 DDEIS High Voltage Setting #j+27
55 DDEIS High Voltage Setting #j+28
56 DDEIS High Voltage Setting #j+29
57 DDEIS High Voltage Setting #j+30
58 DDEIS High Voltage Setting #j+31
59 DDEIS HV table index of last electron peak
60 DDEIS HV table index of last ion peak
61 DDEIS HV control byte of last electron peak
62 DDEIS HV control byte of last ion peak
63 Side 1 PHA accumulator counts from current MJF, byte 0
64 Side 1 PHA accumulator counts from current MJF, byte 1
65 Side 1 PHA accumulator counts from current MJF, byte 2
66 PHA match count for current MJF
*5 67 LSB of BCI Count at Start of PPA Accum == pp_bcicnt
68 MJFTIM mS LSB
69 MJFTIM mS MSB
*6 70 MJFTIM (Spacecraft Universal Time Code, UTC) LSB
*6 71 MJFTIM (Spacecraft Universal Time Code, UTC) NLSB
*6 72 MJFTIM (Spacecraft Universal Time Code, UTC) NMSB
*6 73 MJFTIM (Spacecraft Universal Time Code, UTC) MSB
74 DUNTIM Time == Offset Sun Time mS LSB
75 DUNTIM Time == Offset Sun Time mS MSB
*6 76 DUNTIM (Spacecraft Universal Time Code, UTC) LSB
*6 77 DUNTIM (Spacecraft Universal Time Code, UTC) NLSB
*7 78 DDSCAN First Descriptor Number of Current DDEIS Cycle
*7 79 DDSCAN Last Descriptor Number of Previous DDEIS Cycle
80 MRCD_num (Most Recently Commanded DDEIS Descriptor, numbered 0-7)
81 PPMRCD_num (Most Recently Commanded PPA Descriptor, numbered 0-3)
82 synch_mjf (LSB of mjf_cnt of next resynchronization)
83 synch_mjf (MSB of mjf_cnt of next resynchronization)
84 BCI Control Register LSB
85 BCI Control Register MSB

86 ET2 (PPA) Control Register LSB
87 ET2 (PPA) Control Register MSB
88 DDEIS Descriptor Byte 0
89 DDEIS Descriptor Byte 1
90 DDEIS Descriptor Byte 2
91 DDEIS Descriptor Byte 3
92 DDEIS Descriptor Byte 4
93 DDEIS Descriptor Byte 5
94 DDEIS Descriptor Byte 6
95 DDEIS Descriptor Byte 7
96 DDEIS Descriptor Byte 8
97 DDEIS Descriptor Byte 9
98 DDEIS Descriptor Byte 10
99 DDEIS Descriptor Byte 11
100 DDEIS Descriptor Byte 12
101 PPA Descriptor Byte 0
102 PPA Descriptor Byte 1
103 PPA Descriptor Byte 2
104 PPA Descriptor Byte 3
105 PPA Descriptor Byte 4
106 PPA Descriptor Byte 5
107 PPA Descriptor Byte 6
108 PPA Descriptor Byte 7
109 PPA Descriptor Byte 8
110 PPA Descriptor Byte 9
111 PPA Descriptor Byte 10
112 PPA Descriptor Byte 11
113 PPA Descriptor Byte 12 (null byte)
*2 114 Number of the DDEIS Descriptor being dumped this MJF (see 88-113)
*3 115 Memory Dump Byte #k
*4 116 Scheduler Table Entry #n LSB
117 Scheduler Table Entry #n MSB
118 Status Table Entry #n LSB
119 Status Table Entry #n MSB
120 Address Table Entry #n LSB
121 Address Table Entry #n NLSB
122 Address Table Entry #n NMSB
123 Address Table Entry #n MSB
124 Stack Pointer Table Entry #n LSB
125 Stack Pointer Table Entry #n NLSB
126 Stack Pointer Table Entry #n NMSB
127 Stack Pointer Table Entry #n MSB
128 Error Table Entry #n 1 Byte only
*6 129 DDCYCTIM DD Scan Offset Cycle Start Time mS LSB
*6 130 DDCYCTIM DD Scan Offset Cycle Start Time mS MSB
*6 131 DDCYCTIM (Spacecraft Universal Time Code, UTC) LSB
*6 132 DDCYCTIM (Spacecraft Universal Time Code, UTC) NLSB
133 MJF MSB
*8 134 DDEIS deflection voltage lookup table byte dump
*9 135 HV A/D readback
136 Mode Number, LSB
137 Mode Number, MSB

- *1 Note that j = 0, 32, 64, 96, 128, 160, 192, 224 and then repeats. These values are offsets into dd_hv_array, the array of ddeis hv values saved by ddscan.
For the default descriptors, the 32 values represent one-eighth of a Major Frame. The hv values are saved in the format used by the ddeis hv DAC.
- *2 Expect 0-127. Note this is different from ModeZero.
PPA descr. # = (DDEIS descr. #) mod 32 (Expect 0-31)
- *3 Note that k = 0, 1, 2,..., 8176 and then repeats, since the memory dump is only of 8Kb of ROM.
- *4 Note that n cycles from 0 to 15, since that is the number of entries in the task tables.
- *5 Expect values of 128, 0, 128, 0 for pp_bcicnt
- *6 See S175_2.5.0. thru S175_2.5.3. for description of timing and reference marks.
- *7 Each time a new DDEIS offset cycle begins, the present and previous descriptor numbers are written to memory. These numbers are read out to telemetry once per MJF. With the timing mark, DDCYCTIM, given in words 129-132 and referred to in S175_2.5.1., this creates a timing reference in the scan sequence.
- *8 The DDEIS deflection voltage lookup table is read out one byte per MJF. The identity of the byte is given by the LSB of the major frame counter in the UNH portion of the telemetry format.
- *9 Must be decoded using the 3 lsb's of the MJF. When bit 2 (using the convention that bit 0 is lsb) of the MJF is 0, the byte is from DD; when 1, it is from PP. Low 2 bits of MJF indicate position of tlm byte 135 in the 4 byte value, with 0 being the lsbyte, 3 the msbyte. See HVMON_3.4.FID.

REPORT DOCUMENTATION PAGE

*Form Approved
OMB No. 0704-0188*

Public reporting burden for this collection of information is estimated to average 1 hour per response, including the time for reviewing instructions, searching existing data sources, gathering and maintaining the data needed, and completing and reviewing the collection of information. Send comments regarding this burden estimate or any other aspect of this collection of information, including suggestions for reducing this burden, to Washington Headquarters Services, Directorate for Information Operations and Reports, 1215 Jefferson Davis Highway, Suite 1204, Arlington, VA 22202-4302, and to the Office of Management and Budget, Paperwork Reduction Project (0704-0188), Washington, DC 20503.

| | | | | | | |
|--|--|---|--|--|--|--|
| 1. AGENCY USE ONLY (Leave blank) | | | 2. REPORT DATE September 1996 | | 3. REPORT TYPE AND DATES COVERED Contractor Report | |
| 4. TITLE AND SUBTITLE Software for the Hydra Instrument on the Polar Spacecraft | | | 5. FUNDING NUMBERS NAS5-30549 | | | |
| 6. AUTHOR(S) PI: Walker Fillius | | | 8. PERFORMING ORGANIZATION REPORT NUMBER | | | |
| 7. PERFORMING ORGANIZATION NAME(S) AND ADDRESS (ES) University of California, San Diego Center for Astrophysics and Space Sciences 9500 Gilman Drive La Jolla, California 92093-0111 | | | 10. SPONSORING / MONITORING AGENCY REPORT NUMBER CR-203908 | | | |
| 9. SPONSORING / MONITORING AGENCY NAME(S) AND ADDRESS (ES) National Aeronautics and Space Administration Washington, DC 20546-0001 | | | 11. SUPPLEMENTARY NOTES | | | |
| 12a. DISTRIBUTION / AVAILABILITY STATEMENT Unclassified - Unlimited Subject Category: 90 Report available from the NASA Center for AeroSpace Information, 800 Elkridge Landing Road, Linthicum Heights, MD 21090; (301) 621-0390. | | | 12b. DISTRIBUTION CODE | | | |
| 13. ABSTRACT (Maximum 200 words) Final Technical Report for NAS5-30549 entitled, "Hydra Instrument on the Polar Spacecraft." This software was developed by UCSD for the Hydra instrument and conforms with the contractual Statement of Work, with the exception, ordered by the NASA Technical Monitor, that the programming language was assembly language rather than Forth. | | | | | | |
| 14. SUBJECT TERMS Hydra instrument, software, documentation, Polar spacecraft | | | | | 15. NUMBER OF PAGES 118 | |
| | | | | | 16. PRICE CODE | |
| 17. SECURITY CLASSIFICATION OF REPORT Unclassified | | 18. SECURITY CLASSIFICATION OF THIS PAGE Unclassified | | 19. SECURITY CLASSIFICATION OF ABSTRACT Unclassified | | |
| | | | | | | |
| | | | | 20. LIMITATION OF ABSTRACT UL | | |